



Elektrobit

EB tresos[®] AutoCore Generic 8 DCCM documentation

product release 8.8.3



Elektrobit Automotive GmbH
Am Wolfsmantel 46
91058 Erlangen, Germany
Phone: +49 9131 7701 0
Fax: +49 9131 7701 6333
Email: info.automotive@elektrobit.com

Technical support

<https://www.elektrobit.com/support>

Legal disclaimer

Confidential information.

ALL RIGHTS RESERVED. No part of this publication may be copied in any form, by photocopy, microfilm, retrieval system, or by any other means now known or hereafter invented without the prior written permission of Elektrobit Automotive GmbH.

All brand names, trademarks, and registered trademarks are property of their rightful owners and are used only for description.

Copyright 2021, Elektrobit Automotive GmbH.

Table of Contents

1. Overview of EB tresos AutoCore Generic 8 DCCM documentation	9
2. Supported features	10
3. ACG8 DCCM release notes	12
3.1. Overview	12
3.2. Scope of the release	12
3.2.1. Configuration tool	12
3.2.2. AUTOSAR modules	12
3.2.3. EB (Elektrobit) modules	12
3.2.4. MCAL modules and EB tresos AutoCore OS	13
3.3. Module release notes	13
3.3.1. Dccm module release notes	13
3.3.1.1. Change log	13
3.3.1.2. New features	14
3.3.1.3. EB-specific enhancements	15
3.3.1.4. Deviations	15
3.3.1.5. Limitations	15
3.3.1.6. Open-source software	17
4. ACG8 DCCM user guide	18
4.1. Overview	18
4.2. Background	18
4.2.1. Integration interfaces	18
4.2.2. Files of the Dccm	19
4.2.3. External identifiers	20
4.2.3.1. Platform types	20
4.2.3.2. Compiler abstraction	20
4.2.3.3. Memory mapping	21
4.2.3.4. ComStack types	21
4.2.4. External modules	22
4.2.4.1. PduR	22
4.2.4.2. Rte	22
4.2.5. General functions	22
4.2.6. State machine of a diagnostic protocol	23
4.2.7. Sequence diagram of a request	25
4.2.8. TesterPresent message	27
4.2.9. Input/output buffer	27
4.2.10. Timing parameters	27
4.2.10.1. DccmTimeoutP2Client	27
4.2.10.2. DccmTimeoutP2StarClient	28
4.2.10.3. DccmTimeoutP6Client	28

4.2.10.4. DccmTimeoutP6StarClient	28
4.2.10.5. Internal timeout	28
4.3. Configuring the Dccm module	29
4.3.1. Configuring general values	29
4.3.1.1. Periodic task time	29
4.3.1.2. Enable development error detection	29
4.3.1.3. Number of parallel diagnostic protocols supported	29
4.3.1.4. Number of protocols reserved for functional communication	29
4.3.1.5. Enable buffer streaming	30
4.3.1.6. Functional communication with no response from the server	30
4.3.2. Configuring Dccm timing parameters	30
4.3.3. Configuring a UDS connection	32
4.3.3.1. UDS physical connection	32
4.3.3.1.1. DccmPhysicalPdualds	32
4.3.3.2. UDS functional connection	33
4.3.3.2.1. DccmFunctionalPdualds	33
5. ACG8 DCCM module references	34
5.1. Overview	34
5.1.1. Notation in EB module references	34
5.1.1.1. Default value of configuration parameters	34
5.1.1.2. Range information of configuration parameters	34
5.2. Dccm	35
5.2.1. Configuration parameters	35
5.2.1.1. CommonPublishedInformation	35
5.2.1.2. DccmGeneral	38
5.2.1.3. DccmTimeouts	41
5.2.1.4. DccmP2Client	42
5.2.1.5. DccmP6Client	43
5.2.1.6. DccmPhysicalPdualds	44
5.2.1.7. DccmFunctionalPdualds	45
5.2.1.8. PublishedInformation	46
5.2.2. Application programming interface (API)	46
5.2.2.1. Type definitions	47
5.2.2.1.1. Dccm_BufferStreamingCallbackType	47
5.2.2.1.2. Dccm_CallbackType	47
5.2.2.1.3. Dccm_DiagProtocolResponseCodeType	47
5.2.2.1.4. Dccm_DiagnosticProtocolStatusType	47
5.2.2.1.5. Dccm_ProtocolIdType	47
5.2.2.1.6. Dccm_TimeoutType	48
5.2.2.2. Macro constants	48
5.2.2.2.1. BITS3210_BIT_MASK	48
5.2.2.2.2. BITS_TO_SHIFT_4	48

5.2.2.2.3. BITS_TO_SHIFT_8	48
5.2.2.2.4. DCCM_BIT_MAPPED_REPORTED_WITH_OUT_MASK	48
5.2.2.2.5. DCCM_BUFFER_STREAMING	48
5.2.2.2.6. DCCM_CLEAR_DYNAMICALLY_DEFINED_DATA_IDENTIFIER	49
5.2.2.2.7. DCCM_DEFINE_BY_IDENTIFIER	49
5.2.2.2.8. DCCM_DEFINE_BY_MEMORY_ADDRESS	49
5.2.2.2.9. DCCM_DEV_ERROR_DETECT	49
5.2.2.2.10. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_ALLOCATING	49
5.2.2.2.11. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_READY	49
5.2.2.2.12. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_READY_TO_TRANSMIT	50
5.2.2.2.13. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_RECEIVE	50
5.2.2.2.14. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_RELEASE	50
5.2.2.2.15. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_SEND_NOTIFY	50
5.2.2.2.16. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_SEND_RECEIVED	50
5.2.2.2.17. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_TRANSMIT	50
5.2.2.2.18. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_TRANSMIT_REQUEST_NEXT_BUFFER	51
5.2.2.2.19. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_UNUSED	51
5.2.2.2.20. DCCM_DTCFORMAT_2	51
5.2.2.2.21. DCCM_DTCFORMAT_4	51
5.2.2.2.22. DCCM_EXE_INTERVAL	51
5.2.2.2.23. DCCM_E_INVALID_RESPONSE_FORMAT	51
5.2.2.2.24. DCCM_E_INVALID_RESPONSE_LENGTH	52
5.2.2.2.25. DCCM_E_RESPONSE_PENDING	52
5.2.2.2.26. DCCM_FUNCTIONAL_COMM_NO_RESPONSE_EXPECTED	52
5.2.2.2.27. DCCM_INVALID_PROTOCOL_ID	52
5.2.2.2.28. DCCM_LENGTH_0	52
5.2.2.2.29. DCCM_LENGTH_1	52
5.2.2.2.30. DCCM_LENGTH_2	53
5.2.2.2.31. DCCM_LENGTH_3	53
5.2.2.2.32. DCCM_LENGTH_4	53
5.2.2.2.33. DCCM_LENGTH_5	53
5.2.2.2.34. DCCM_LENGTH_6	53
5.2.2.2.35. DCCM_LENGTH_7	53
5.2.2.2.36. DCCM_LENGTH_8	53
5.2.2.2.37. DCCM_MAX_DIAGNOSTIC_PROTOCOLS	54
5.2.2.2.38. DCCM_MAX_DTC_EXT_DATA_RECORD_NR_16	54
5.2.2.2.39. DCCM_MAX_DTC_EXT_DATA_RECORD_NR_19	54
5.2.2.2.40. DCCM_MAX_DTC_EXT_DATA_RECORD_NR_6_10	54
5.2.2.2.41. DCCM_MAX_PHYSICAL_DIAGNOSTIC_PROTOCOLS	54

5.2.2.2.42. DCCM_MAX_SERVERS_FUNCTIONAL_ADDRESSING	54
5.2.2.2.43. DCCM_MAX_SERVERS_PHYSICAL_ADDRESSING	55
5.2.2.2.44. DCCM_MODE_OF_OPERATION_DELETE_FILE	55
5.2.2.2.45. DCCM_MODE_OF_OPERATION_READ_DIR	55
5.2.2.2.46. DCCM_P2CLIENT_ENABLED	55
5.2.2.2.47. DCCM_P6CLIENT_ENABLED	55
5.2.2.2.48. DCCM_READ_CURRENTLY_ACTIVE_TIMING_PARAMETERS	55
5.2.2.2.49. DCCM_READ_EXTEND_TIMING_PARAMETER_SET	56
5.2.2.2.50. DCCM_RETRY_INFO_NULL	56
5.2.2.2.51. DCCM_RSP_INVALID_RESPONSE_PENDING_FORMAT	56
5.2.2.2.52. DCCM_RSP_OK	56
5.2.2.2.53. DCCM_RSP_RX_FAILED	56
5.2.2.2.54. DCCM_RSP_TIMEOUT	56
5.2.2.2.55. DCCM_RSP_TIMEOUT_INTERNAL	57
5.2.2.2.56. DCCM_RSP_TIMEOUT_P2CLIENT	57
5.2.2.2.57. DCCM_RSP_TIMEOUT_P6CLIENT	57
5.2.2.2.58. DCCM_RSP_TX_FAILED	57
5.2.2.2.59. DCCM_RSP_TX_TRIG_FAILED	57
5.2.2.2.60. DCCM_RSP_WRONG_BUFFER_SIZE	58
5.2.2.2.61. DCCM_SCALING_BYTE_FORMULA	58
5.2.2.2.62. DCCM_SCALING_BYTE_UNIT_FORMAT	58
5.2.2.2.63. DCCM_SERVICE_ECU_RESET_SUBFUNCTION_ENABLE_RAPID_POWER_SHUTDOWN	58
5.2.2.2.64. DCCM_STD_E_BUSY	58
5.2.2.2.65. DCCM_SUBFUNCTION_MASK	58
5.2.2.2.66. DCCM_SUPPRESSBIT_MASK	59
5.2.2.2.67. DCCM_TIMEOUT_INTERNAL	59
5.2.2.2.68. DCCM_TIMEOUT_P2CLIENT	59
5.2.2.2.69. DCCM_TIMEOUT_P2STARCLIENT	59
5.2.2.2.70. DCCM_TIMEOUT_P6CLIENT	59
5.2.2.2.71. DCCM_TIMEOUT_P6STARCLIENT	59
5.2.2.2.72. DCCM_TX_CONFIRMATION_OK	59
5.2.2.2.73. DCCM_ZERO_SUBFUNCTION	60
5.2.2.2.74. Dccm_ProvideRxBuffer	60
5.2.2.2.75. Dccm_ProvideTxBuffer	60
5.2.2.2.76. FUNCTIONAL_ADDRESSING	60
5.2.2.2.77. MAX_NO_OF_SERVICES	60
5.2.2.2.78. NEGATIVE_RESPONSE_LENGTH	60
5.2.2.2.79. NEGATIVE_RESPONSE_SID	61
5.2.2.2.80. PHYSICAL_ADDRESSING	61
5.2.2.2.81. SID_ACCESS_TIMING_PARAMETER	61

5.2.2.2.82. SID_ACCESS_TIMING_PARAMETER_RSP	61
5.2.2.2.83. SID_CLEAR_DIAGNOSTIC_INFORMATION	61
5.2.2.2.84. SID_CLEAR_DIAGNOSTIC_INFORMATION_RSP	61
5.2.2.2.85. SID_COMMUNICATION_CONTROL	61
5.2.2.2.86. SID_COMMUNICATION_CONTROL_RSP	62
5.2.2.2.87. SID_CONTROL_DTC_SETTING	62
5.2.2.2.88. SID_CONTROL_DTC_SETTING_RSP	62
5.2.2.2.89. SID_DIAGNOSTIC_SESSION_CONTROL	62
5.2.2.2.90. SID_DIAGNOSTIC_SESSION_CONTROL_RSP	62
5.2.2.2.91. SID_DYNAMICALLY_DEFINE_DATA_IDENTIFIER	62
5.2.2.2.92. SID_DYNAMICALLY_DEFINE_DATA_IDENTIFIER_RSP	63
5.2.2.2.93. SID_ECU_RESET	63
5.2.2.2.94. SID_ECU_RESET_RSP	63
5.2.2.2.95. SID_FILE_TRANSFER	63
5.2.2.2.96. SID_FILE_TRANSFER_RSP	63
5.2.2.2.97. SID_INPUT_OUTPUT_CONTROL_BY_IDENTIFIER	63
5.2.2.2.98. SID_INPUT_OUTPUT_CONTROL_BY_IDENTIFIER_RSP	63
5.2.2.2.99. SID_LINK_CONTROL	64
5.2.2.2.100. SID_LINK_CONTROL_RSP	64
5.2.2.2.101. SID_READ_DATA_BY_IDENTIFIER	64
5.2.2.2.102. SID_READ_DATA_BY_IDENTIFIER_RSP	64
5.2.2.2.103. SID_READ_DATA_BY_PERIODIC_IDENTIFIER	64
5.2.2.2.104. SID_READ_DATA_BY_PERIODIC_IDENTIFIER_RSP	64
5.2.2.2.105. SID_READ_DTC_INFORMATION	65
5.2.2.2.106. SID_READ_DTC_INFORMATION_RSP	65
5.2.2.2.107. SID_READ_MEMORY_BY_ADDRESS	65
5.2.2.2.108. SID_READ_MEMORY_BY_ADDRESS_RSP	65
5.2.2.2.109. SID_READ_SCALING_DATA_BY_IDENTIFIER	65
5.2.2.2.110. SID_READ_SCALING_DATA_BY_IDENTIFIER_RSP	65
5.2.2.2.111. SID_REQUEST_DOWNLOAD	65
5.2.2.2.112. SID_REQUEST_DOWNLOAD_RSP	66
5.2.2.2.113. SID_REQUEST_TRANSFER_EXIT	66
5.2.2.2.114. SID_REQUEST_TRANSFER_EXIT_RSP	66
5.2.2.2.115. SID_REQUEST_UPLOAD	66
5.2.2.2.116. SID_REQUEST_UPLOAD_RSP	66
5.2.2.2.117. SID_RESPONSE_ON_EVENT	66
5.2.2.2.118. SID_RESPONSE_ON_EVENT_RSP	66
5.2.2.2.119. SID_ROUTINE_CONTROL	67
5.2.2.2.120. SID_ROUTINE_CONTROL_RSP	67
5.2.2.2.121. SID_SECURED_DATA_TRANSMISSION	67
5.2.2.2.122. SID_SECURED_DATA_TRANSMISSION_RSP	67
5.2.2.2.123. SID_SECURITY_ACCESS	67

5.2.2.2.124. SID_SECURITY_ACCESS_RSP	67
5.2.2.2.125. SID_TESTER_PRESENT	67
5.2.2.2.126. SID_TESTER_PRESENT_RSP	68
5.2.2.2.127. SID_TRANSFER_DATA	68
5.2.2.2.128. SID_TRANSFER_DATA_RSP	68
5.2.2.2.129. SID_WRITE_DATA_BY_IDENTIFIER	68
5.2.2.2.130. SID_WRITE_DATA_BY_IDENTIFIER_RSP	68
5.2.2.2.131. SID_WRITE_MEMORY_BY_ADDRESS	68
5.2.2.2.132. SID_WRITE_MEMORY_BY_ADDRESS_RSP	68
5.2.2.3. Functions	69
5.2.2.3.1. Dccm_AllocateDiagnosticProtocol	69
5.2.2.3.2. Dccm_CheckBufferSuppressBit	70
5.2.2.3.3. Dccm_CheckResponsePending	71
5.2.2.3.4. Dccm_CopyRxData	71
5.2.2.3.5. Dccm_CopyTxData	72
5.2.2.3.6. Dccm_DisableTesterPresent	73
5.2.2.3.7. Dccm_EnableTesterPresent	74
5.2.2.3.8. Dccm_GetDiagnosticProtocolStatus	75
5.2.2.3.9. Dccm_Init	75
5.2.2.3.10. Dccm_IsTesterPresentEnabled	76
5.2.2.3.11. Dccm_MainFunction	76
5.2.2.3.12. Dccm_ReleaseAllDiagnosticProtocols	77
5.2.2.3.13. Dccm_ReleaseDiagnosticProtocol	77
5.2.2.3.14. Dccm_RxIndication	78
5.2.2.3.15. Dccm_SendRequest	78
5.2.2.3.16. Dccm_SetCommunicationTimeoutParameters	79
5.2.2.3.17. Dccm_SetTesterPresentInterval	80
5.2.2.3.18. Dccm_StartOfReception	81
5.2.2.3.19. Dccm_TxConfirmation	81
5.2.2.3.20. Dccm_ValidateRespBasedOnRequest	82
5.2.3. Integration notes	83
5.2.3.1. Exclusive areas	83
5.2.3.2. Production errors	83
5.2.3.3. Memory mapping	83
5.2.3.4. Integration requirements	83
5.2.3.5. Platform integration	84
Bibliography	85



1. Overview of EB tresos AutoCore Generic 8 DCCM documentation

Welcome to the EB tresos AutoCore Generic 8 DCCM (ACG8 DCCM) product documentation.

This document provides:

- ▶ [Chapter 2, “Supported features”](#): list of features supported by ACG8 DCCM
- ▶ [Chapter 3, “ACG8 DCCM release notes”](#): release notes for the ACG8 DCCM module
- ▶ [Chapter 4, “ACG8 DCCM user guide”](#): background information and instructions
- ▶ [Chapter 5, “ACG8 DCCM module references”](#): configuration parameters and the application programming interface

2. Supported features

- ▶ **Multiple parallel requests:** Dccm supports up to 255 parallel requests.
- ▶ **Generic send request:** Any UDS payload can be built and provided to the Dccm for communication.
- ▶ **Functional and physical communication:** Dccm supports both functional and physical addressing.
- ▶ **Periodic tester present:** Functional communication channels can be configured to send a periodic tester present message.
- ▶ **Buffer streaming:** Dccm can be configured for streaming.
- ▶ **Suppress positive response message indication bit:** Dccm supports the `suppressPosResponseMessageIndicationBit`.
- ▶ **Request correctly received response pending:** Dccm supports the negative response code RCRRP (`requestCorrectlyReceivedResponsePending`).
- ▶ **Communication interface for UDS services:** Dccm supports the following UDS services:
 - ▶ SID \$10 - DiagnosticSessionControl
 - ▶ SID \$11 - ECUReset
 - ▶ SID \$27 - SecurityAccess
 - ▶ SID \$28 - CommunicationControl
 - ▶ SID \$3E - TesterPresent
 - ▶ SID \$83 - AccessTimingParameter
 - ▶ SID \$84 - SecuredDataTransmission
 - ▶ SID \$85 - ControlDTCSetting
 - ▶ SID \$87 - LinkControl
 - ▶ SID \$22 - ReadDataByIdentifier
 - ▶ SID \$23 - ReadMemoryByAddress
 - ▶ SID \$24 - ReadScalingDataByIdentifier
 - ▶ SID \$2C - DynamicallyDefineDataIdentifier
 - ▶ SID \$2E - WriteDataByIdentifier
 - ▶ SID \$3D - WriteMemoryByAddress
 - ▶ SID \$14 - ClearDiagnosticInformation
 - ▶ SID \$19 - ReadDTCInformation
 - ▶ SID \$2F - InputOutputControlByIdentifier
 - ▶ SID \$31 - RoutineControl

- ▶ SID \$34 - RequestDownload
- ▶ SID \$35 - RequestUpload
- ▶ SID \$36 - TransferData
- ▶ SID \$37 - RequestTransferExit
- ▶ SID \$38 - RequestFileTransfer
- ▶ **Configurable timing parameters:** `Dccm` supports the following parameters:
 - ▶ P2Client
 - ▶ P2*Client
 - ▶ P6Client
 - ▶ P6*Client
 - ▶ InternalTimeout
- ▶ **Validation of the request and response messages** `Dccm` offer support for a filtering mechanism according with ISO 14229-1 to guarantee that only allowed request are send. Based on the request, the response will be verified. The validation is possible using `Dccm_ValidateRespBasedOnRequest` API.

3. ACG8 DCCM release notes

3.1. Overview

This chapter provides the ACG8 DCCM product specific release notes. General release notes that are applicable to all products are provided in the EB tresos AutoCore Generic documentation. Refer to the general release notes in addition to the product release notes documented here.

3.2. Scope of the release

3.2.1. Configuration tool

Your release of EB tresos AutoCore is compatible with the release of the EB tresos Studio configuration tool:

- ▶ EB tresos Studio: 28.1.0 b210701-0227

3.2.2. AUTOSAR modules

The following table lists the AUTOSAR modules that are part of this ACG8 DCCM release.

Module name	AUTOSAR version and revision	SWS version and revision	Module version	Supplier
No AUTOSAR modules available				

Table 3.1. Hardware-Independent Modules specified by the AUTOSAR standard

3.2.3. EB (Elektrobit) modules

The following table lists all modules which are part of this release but are not specified by the AUTOSAR standard. These modules include tooling developed by EB or they may hold files shared by all other modules.

Module name	Module version	Supplier
Dccm	2.0.6	Elektrobit Automotive GmbH

Table 3.2. Modules not specified by the AUTOSAR standard

3.2.4. MCAL modules and EB tresos AutoCore OS

For information about MCAL modules and OS, refer to the respective documentation, which is available as PDF at `$TRESOS_BASE/doc/3.0_EB_tresos_AutoCore_OS` and `$TRESOS_BASE/doc/5.0_MCAL_modules`¹. It is also available in the online help in EB tresos Studio. Browse to the folders `EB tresos AutoCore OS` and `MCAL modules`.

3.3. Module release notes

3.3.1. Dccm module release notes

- ▶ Module version: 2.0.6.B439717
- ▶ Supplier: Elektrobit Automotive GmbH

3.3.1.1. Change log

This chapter lists the changes between different versions.

Module version 2.0.6

2021-04-30

- ▶ Added support for `P6Client` and `P6*Client` timing parameters.

Module version 2.0.5

2021-03-05

- ▶ Internal module improvement. This module version update does not affect module functionality.

Module version 2.0.4

2020-10-23

- ▶ Added support for response and request validation. `Dccm_ValidateRespBasedOnRequest()` API is now available.

¹`$TRESOS_BASE` is the location at which you installed EB tresos Studio.

- ▶ Update the configuration files. The configuration tables for functional and physical Pdulds are in the same tab. RxPdulld and TxPdulld are easier to be allocated for a specific Pdulld.
- ▶ The signature for Dccm_SendRequest() API was changed, parameter AddressingType was removed.

Module version 2.0.3

2020-03-25

- ▶ Replaced the `Default Timeout` and `Default Negative Timeout` with `P2Client` and `P2*Client`.

Module version 2.0.2

2020-01-24

- ▶ Changed the module name from UdsC to Dccm.

Module version 2.0.1

2019-09-30

- ▶ Changed the signature for the `Dccm_AllocateDiagnosticProtocol()` API. The `BufferStreaming-Callback` parameter is now mandatory. If the `BufferStreaming` is not activated, this pointer should be null.

Module version 2.0.0

2019-04-10

- ▶ AUTOSAR 4.0.3 version.

Module version 1.0.0

2018-03-14

- ▶ Initial AUTOSAR 4.0 version.

3.3.1.2. New features

- ▶ Support for P6Client and P6*Client timing parameters

Description:

The Dccm module is extended offering support for two new timeout parameters: P6Client and P6*Client.

3.3.1.3. EB-specific enhancements

This module is not part of the AUTOSAR specification.

3.3.1.4. Deviations

This module is not part of the AUTOSAR specification.

3.3.1.5. Limitations

This chapter lists the limitations of the module. Refer to the module references chapter *Integration notes*, subsection *Integration requirements* for requirements on integrating this module.

- ▶ **A unique request for a single protocol**

Description:

When a protocol processes a request, it does not allow another request to be processed at the same time.

- ▶ **Unsupported UDS services**

Description:

The current version of Dccm does not support the following UDS services:

- ▶ ResponseOnEvent
- ▶ ReadDataByPeriodicIdentifier

- ▶ **Maximum number of parallel diagnostic protocols**

Description:

The maximum number of parallel diagnostic protocols can be configured but is limited to maximum 255.

- ▶ **Diagnostic protocols**

Description:

The application that is the client of Dccm cannot communicate with a server without first allocating a diagnostic protocol. The number of available diagnostic protocols is limited by:

- ▶ the total number of protocols that is configured for the Dccm module
- ▶ the number of protocols previously allocated by the client application
- ▶ the number of protocols reserved for functional communication (from the configuration of Dccm)

- ▶ **Communication type**

Description:

From the total number of protocols, the client of the Dccm module can use any number of protocols for functional communication. The number of protocols available for physical communication is the difference between the total number of protocols and the number of protocols reserved for functional communication.

► **Limitation suppressPosRspMsgIndication**

Description:

If the suppressPosRspMsgIndication is set to TRUE, Dccm no longer listens to the server responses but sends to the client a notification with a response code. The Dccm protocol status is changed to DCCM_DIAGNOSTIC_PROTOCOL_STATUS_READY. If the server wants to send a negative response, is not possible because the StartOfReception() API can only be used if the Dccm protocol has the status DCCM_DIAGNOSTIC_PROTOCOL_STATUS_RECEIVE. This also applies to the NRC 0x78 (requestCorrectlyReceived-ResponsePending RCRRP).

► **ISO timers**

Description:

Dccm implements only P2Client, P2*Client, P6Client and P6*Client timers according to ISO14229-2 (2013). Any other timers mentioned in ISO14229-2 are not supported.

For functional addressing, the handling for P2Client, P2*Client, P6Client and P6*Client is not different compared to physical communication (cf. chapter 8.2 Functional communication, ISO14229-2, 2013).

► **Recommendation for a generic client error handling**

Description:

Dccm does not handle errors as recommended in "Table 9 - Recommendation for a generic client error handling" (ISO14229-2, 2013). Dccm sends the error code to the client of the Dccm, and does not do any repeat of the request.

► **Maximum request length**

Description:

The maximum amount of data that can be sent using the Dccm_SendRequest() API is 65535 bytes.

► **Functional addressing limitations**

Description:

During functional addressing, Dccm sends the messages to a functional address. The system is responsible to broadcast the messages to the relevant servers. After sending a functional message, Dccm will wait or not for responses from the functional address, based on Dccm's configuration parameter Dccm_Functional_Communication_With_No_Response_From_Server. Dccm will not wait for responses from other servers, other than the functional address.

(Cf. Table 5 - Functionally addressed request message with sub-function parameter and server response behaviour and Table 7 - Functionally addressed request message without sub-function parameter and server response behaviour, ISO14229-1, 2013)

► **Negative response code 0x21 busyRepeatRequest**

Description:

Dccm does not perform any special handling when the negative response code busyRepeatRequest is received. The response is forwarded to the client of the Dccm.

3.3.1.6. Open-source software

Dccm does not use open-source software.

4. ACG8 DCCM user guide

4.1. Overview

This document gives a short overview of the `Dccm` module. From this user guide you will learn about the basic functionality of the `Dccm`. You will also learn which related modules are necessary to configure the `Dccm` module. The `Dccm` module reference provides further information on configuring the `Dccm` itself.

Note that this user guide is intended for readers who have good knowledge of AUTOSAR and about the purpose of the `Dccm`. The information provided here should help you to integrate the `Dccm` in your AUTOSAR project.


4.2. Background

The Unified Diagnostic Services (UDS) are standardized as part of ISO 14229-1 [\[4\]](#). With UDS, a tester (client) has the ability to control diagnostic functions in an on-vehicle Electronic Control Unit (server).

The Diagnostic Client Communication Manager (`Dccm`) module provides a UDS communication library that can speed up the development of a UDS client.

4.2.1. Integration interfaces

Before you can use the `Dccm`, you must integrate it into the software environment. The following picture provides an overview of the integration interfaces:



The green box represents the DCCM. All functions of the DCCM that have to be called are shown.

The white boxes represent the modules of the standard software. The arrows show which functions of those modules are called by the DCCM and which functions of the DCCM have to be called by the modules. For a description of the interactions, see [Section 4.2.4, “External modules”](#).

4.2.2. Files of the Dccm

The DCCM consists of the following source files, which have to be compiled to obtain the full functionality. The DCCM configuration files are generated by EB tresos Studio.

► Core files:

- Dccm.h
- Dccm_Cbk.h
- Dccm_Internal.h
- Dccm_MainFunction.c
- Dccm_Cbk.c
- Dccm_Service.c
- Dccm_Validation.c

► Configuration files:

- Dccm_Cfg.h

4.2.3. External identifiers

The Dccm uses certain external identifiers that have to be provided by the software environment. The Dccm uses only external identifiers that would be provided by a complete AUTOSAR environment.

4.2.3.1. Platform types

The Dccm uses platform types as described in [1]. To obtain those types, it includes the file `Std_Types.h`. The following subset of types is used:

- ▶ `uint8`
- ▶ `uint16`
- ▶ `uint32`
- ▶ `boolean`
- ▶ `Std_ReturnType`

The following subset of macros is used:

- ▶ `TRUE`
- ▶ `FALSE`
- ▶ `E_OK`
- ▶ `E_NOT_OK`

4.2.3.2. Compiler abstraction

The Dccm uses compiler abstraction macros as described in [2]. To obtain those types, it includes the file `Std_Types.h`. The following subset of macros is used:

- ▶ `FUNC`
- ▶ `P2VAR`
- ▶ `P2FUNC`
- ▶ `CONST`
- ▶ `VAR`
- ▶ `STATIC`
- ▶ `AUTOMATIC`
- ▶ `STD_ON`

- ▶ `STD_OFF`

The `Dccm` uses the following `Dccm`-specific macros that also have to be defined:

- ▶ `DCCM_VAR`
- ▶ `DCCM_CODE`
- ▶ `DCCM_APPL_DATA`

4.2.3.3. Memory mapping

The `Dccm` uses memory mapping as described in [3]. For this, it includes the file `MemMap.h`. The following macros are used:

- ▶ `DCCM_START_SEC_CODE/DCCM_STOP_SEC_CODE`
- ▶ `DCCM_START_SEC_VAR_UNSPECIFIED/DCCM_STOP_SEC_VAR_UNSPECIFIED`
- ▶ `DCCM_START_SEC_CONST_UNSPECIFIED/DCCM_STOP_SEC_CONST_UNSPECIFIED`
- ▶ `DCCM_START_SEC_VAR_NO_INIT_UNSPECIFIED/DCCM_STOP_SEC_VAR_NO_INIT_UNSPECIFIED`

4.2.3.4. ComStack types

The `Dccm` interacts with the `PduR` module. For this, it includes the file `ComStack_Types.h`. The following macros are used:

- ▶ `NTFRSLT_OK`
- ▶ `NTFRSLT_E_TIMEOUT_A`
- ▶ `NTFRSLT_E_TIMEOUT_BS`
- ▶ `NTFRSLT_E_TIMEOUT_CR`
- ▶ `TP_DATACONF`
- ▶ `TP_DATARETRY`
- ▶ `TP_CONFPENDING`
- ▶ `BUFREQ_OK`
- ▶ `BUFREQ_E_NOT_OK`
- ▶ `BUFREQ_E_BUSY`

The following types are used:

- ▶ `NotifResultType`

- ▶ `PduIdType`
- ▶ `PduInfoType`
- ▶ `PduLengthType`
- ▶ `RetryInfoType`
- ▶ `TpDataStateType`
- ▶ `BufReq_ReturnType`

4.2.4. External modules

4.2.4.1. PduR

The `Dccm` has to send and receive data. To do this, it uses the `PduR` module. The header files `PduR.h` and `PduR_Dccm.h` are included and the following function is used: `PduR_DccmTransmit()`.

The `PduR` itself has to be configured to work with the `Dccm`. It must include the header file `Dccm_PduR.h` and use the following callback functions of the `Dccm`:

- ▶ `Dccm_CopyRxData()`
- ▶ `Dccm_CopyTxData()`
- ▶ `Dccm_RxIndication()`
- ▶ `Dccm_StartOfReception()`
- ▶ `Dccm_TxConfirmation()`

4.2.4.2. Rte

The `Dccm` has to be triggered cyclically. To do this, it uses the `Rte` module. The `Rte` uses the following function: `Dccm_MainFunction()`.

The `Rte` itself has to be configured to work with the `Dccm`. It must include the header `SchM_Dccm.h`.


4.2.5. General functions

The main function of the `Dccm` has to be called cyclically. To be able to use this function, the header `Dccm.h` has to be included in the application.

The `Dccm` uses a state machine. This means that most of its tasks are requested asynchronously and are actually performed in `Dccm_MainFunction()`. The integrator has to make sure that the `Dccm_MainFunction` is called cyclically by the software environment and that the execution time is defined as [Periodic task time](#).


4.2.6. State machine of a diagnostic protocol

The following diagram describes all possible states of a diagnostic protocol. It also shows how transitions take place.



4.2.7. Sequence diagram of a request

The following diagram describes the entire scenario when a request is sent. It shows the interaction between the `Dccm` module and the other modules involved. The request shown is a request on a physical protocol for any of the supported services.



4.2.8. TesterPresent message

Sending a message to the TesterPresent service can be enabled only for protocols that use functional addressing. The message indicates to the server that the tester is still present and that is necessary to keep the session active.

Specific APIs are:

- ▶ `Dccm_EnableTesterPresent()`
- ▶ `Dccm_SetTesterPresentInterval()`
- ▶ `Dccm_DisableTesterPresent()`
- ▶ `Dccm_IsTesterPresentEnabled()`

4.2.9. Input/output buffer

The `Dccm` client application is responsible to provide an input/output buffer and to maintain the integrity of the buffer for the period of the UDS service request. The `Dccm` client application should estimate the expected amount of return data and provide a buffer of the expected size. The `Dccm` client application should be aware that the buffer data is overwritten by the `Dccm` module during the operation.

4.2.10. Timing parameters

The `Dccm` provides the following timing parameters that are implemented according to [5]:

- ▶ [DccmTimeoutP2Client](#)
- ▶ [DccmTimeoutP2StarClient](#)
- ▶ [DccmTimeoutP6Client](#)
- ▶ [DccmTimeoutP6StarClient](#)

In addition, you can configure an [Internal timeout](#).

For information on how to configure the timing parameters, see [Section 4.3.2, “Configuring Dccm timing parameters”](#).

4.2.10.1. DccmTimeoutP2Client

The `P2Client` represents the maximum amount of time in milliseconds between a successfully transmitted request and the start of the corresponding response. The successful transmission of the request mes-

sage is indicated with `Dccm_TxConfirmation()`. The start of the response message is indicated with `Dccm_StartOfReception()`.

4.2.10.2. DccmTimeoutP2StarClient

The P2*Client represents the maximum amount of time in milliseconds between a response that contains the negative response code 0x78 "requestCorrectlyReceived-ResponsePending" and the start of the next response. The reception of a negative response is indicated with `Dccm_RxIndication()`. The start of an incoming response message is indicated with `Dccm_StartOfReception()`.

4.2.10.3. DccmTimeoutP6Client

The P6Client represents the maximum amount of time in milliseconds between a successfully transmitted request and the complete reception of the corresponding response. The successful transmission of the request message is indicated via `Dccm_TxConfirmation()`. The complete reception of the response message is indicated via `Dccm_RxIndication()`.

4.2.10.4. DccmTimeoutP6StarClient

The P6*Client represents the maximum amount of time in milliseconds between a response containing the negative response code 0x78 "requestCorrectlyReceived-ResponsePending" and the complete reception of the response. The reception of a negative response is indicated via `Dccm_RxIndication()`. The complete reception of the response message is also indicated via `Dccm_RxIndication()`.


4.2.10.5. Internal timeout

This timer starts twice during the processing of a request:

1. between the start of transmission and the confirmation of transmission for a request message
The start of transmission is triggered by the `Dccm` call of `PduR_DccmTransmit()`. The successful transmission of the request message is indicated with `Dccm_TxConfirmation()`.
2. between the start and the end of reception for the response message
The start of the response message is indicated with `Dccm_StartOfReception()`. The end of reception is indicated with `Dccm_RxIndication()`.

4.3. Configuring the Dccm module

4.3.1. Configuring general values



The screenshot shows the 'Dccm General Configuration' window. It has a title bar with a dropdown arrow and the text 'Dccm General Configuration'. Below the title bar is a 'Name*' field with a folder icon and the text 'DccmGeneral'. The main area contains several configuration items, each with a document icon, a label, a value field, and an edit icon (pencil). The items are: 'Periodic Task time (0.001 -> 1)' with a value of '0.005'; 'Enable Development Error Detection' with a checked checkbox; 'Number of Parallel Diagnostic Protocols supported (1 -> 255)' with a value of '20'; 'Number of Protocols reserved for Functional Communication (0 -> 254)*' with a value of '0'; and 'Enable Buffer Streaming*' with a checked checkbox. To the right of the 'Enable Buffer Streaming*' checkbox is a text label 'Functional Communication with no response from the server' followed by a document icon, a checked checkbox, and an edit icon.

4.3.1.1. Periodic task time

With the `Periodic task time` parameter, you configure the scheduling time for the periodic task in seconds.

`DccmTaskTime` affects the scheduling of `Dccm_MainFunction()`. The `Dccm_MainFunction` is executed after every `DccmTaskTime`.

4.3.1.2. Enable development error detection

This parameter enables the error reporting to the Development Error Tracer (`Det`) module.

- ▶ TRUE: Development error detection mechanism is enabled, i.e. switched on.
- ▶ FALSE: Development error detection mechanism is disabled, i.e. switched off.

4.3.1.3. Number of parallel diagnostic protocols supported

This parameter sets the number of parallel diagnostic protocols supported.

4.3.1.4. Number of protocols reserved for functional communication

This parameter sets the number of diagnostic protocols used for functional communication.

The value must be smaller than the number of parallel diagnostic protocols.

4.3.1.5. Enable buffer streaming

With this parameter, you can enable the buffer streaming.

When a `Dccm` request needs to transmit bigger quantity of data and not enough memory is available on the ECU, the buffer streaming can be enabled. This allows the client to provide a smaller buffer when calling the `Dccm_SendRequest()` function. After the buffer data is provided to the `PduR`, the `Dccm` requests the next chunk of data from the client.

- ▶ **TRUE:** Buffer streaming is enabled, i.e. switched on.
- ▶ **FALSE:** Buffer streaming is disabled, i.e. switched off.


4.3.1.6. Functional communication with no response from the server

The server does not send any response for the requests that use functional communication.

- ▶ **TRUE:** In the case of functional communication, `Dccm` takes into account that the server does not send any response. For the messages that are sent to the server, `Dccm` overwrites the value of the bit `suppress-PosRspMsgIndicationBit` with **TRUE**.
- ▶ **FALSE:** `Dccm` takes into account that the server sends a response for functional requests. The `Dccm` does not modify the messages that are sent to the server.


4.3.2. Configuring Dccm timing parameters



For background information on the `Dccm` timing parameters, see [Section 4.2.10, “Timing parameters”](#).





General | **Timeouts** | Connection Configuration | EB Published Information | Published Information



▼ **Configure Dccm Timeouts.**



Name*  DccmTimeouts

Internal Timeout (0 -> 4294967294)*  2000 



▼ **DccmP2Client**



 Name*  DccmP2Client

DccmTimeoutP2Client (1 -> 4294967294)*  1000 

DccmTimeoutP2StarClient (1 -> 4294967294)*  8000 

▼ **DccmP6Client**

 Name*  DccmP6Client

DccmTimeoutP6Client (1 -> 4294967294)*  3000 



DccmTimeoutP6StarClient (1 -> 4294967294)*  5000 

Figure 4.1. Timeout parameters



Configuring a timeout

Step 1

Go to the **Timeouts** tab.

Step 2

Enable the container with the desired client timer:

- ▶ To configure P2Client or P2StarClient timeouts, enable the **DccmP2Client** container.
- ▶ To configure P6Client or P6StarClient timeouts, enable the **DccmP6Client** container.


Step 3

In the desired timeout parameter (see [Figure 4.1, “Timeout parameters”](#)), enter the value in milliseconds.

Step 4

To configure an internal timeout, enter the value in milliseconds in the `Internal Timeout` parameter. If you set the timer value to zero, the timeout is disabled.

4.3.3. Configuring a UDS connection

Name*  Dccm


General










Timeouts





















Connection Configuration


EB Published Information










Published Information



















































 DccmPhysicalPduls

Index	Name	 Eculd	 TxPduld	 TxPduldRef	 RxPduld	 RxPduldRef
0	DccmPhysi...	 0	 0	 /EcuC/Ecu...	 0	 /EcuC/Ecu...
1	DccmPhysi...	 1	 1	 /EcuC/Ecu...	 1	 /EcuC/Ecu...
2	DccmPhysi...	 2	 2	 /EcuC/Ecu...	 2	 /EcuC/Ecu...

 DccmFunctionalPduls

Index	Name	 Eculd	 TxPduld	 TxPduldRef	 RxPduld	 RxPduldRef
0	DccmFunc...	 3	 3	 /EcuC/Ecu...	 3	 /EcuC/Ecu...
1	DccmFunc...	 4	 4	 /EcuC/Ecu...	 4	 /EcuC/Ecu...
2	DccmFunc...	 5	 5	 /EcuC/Ecu...	 5	 /EcuC/Ecu...
3	DccmFunc...	 6	 6	 /EcuC/Ecu...	 6	 /EcuC/Ecu...
4	DccmFunc...	 7	 7	 /EcuC/Ecu...	 7	 /EcuC/Ecu...
5	DccmFunc...	 8	 8	 /EcuC/Ecu...	 8	 /EcuC/Ecu...
6	DccmFunc...	 9	 9	 /EcuC/Ecu...	 9	 /EcuC/Ecu...
7	DccmFunc...	 10	 10	 /EcuC/Ecu...	 10	 /EcuC/Ecu...
8	DccmFunc...	 11	 11	 /EcuC/Ecu...	 11	 /EcuC/Ecu...

4.3.3.1. UDS physical connection

4.3.3.1.1. DccmPhysicalPduls

In the **DccmPhysicalPduls** container, you configure the **Dccm** transmission and reception channels for physical communication.



4.3.3.2. UDS functional connection

4.3.3.2.1. DccmFunctionalPduls

In the **DccmFunctionalPduls** container, you configure the `Dccm` transmission and reception channels for functional communication.

5. ACG8 DCCM module references

5.1. Overview

This chapter provides module references for the ACG8 DCCM product modules. These include a detailed description of all configuration parameters. Furthermore this chapter lists the application programming interface with all data types, constants and functions.

The content of the sections is sorted alphabetically according the EB tresos AutoCore Generic module names.

For further information on the functional behavior of these modules, refer to the chapter ACG8 DCCM user's guide.

5.1.1. Notation in EB module references

EB notation may differ from the AUTOSAR standard notation in the software specification documents (SWS). This section describes the notation of *default value* and *range* fields in the EB module references.

5.1.1.1. Default value of configuration parameters

If there is no default value specified for a parameter, the default value field is omitted to prevent ambiguity with parameters that have -- as default values.

Example: The parameter `BswMCompuConstText` of the `BswM` module of EB tresos AutoCore Generic 8 Mode Management has no default value field, therefore it is omitted.

5.1.1.2. Range information of configuration parameters

The range of a configuration parameter contains an upper and a lower boundary. However, in special cases the range of allowed values can be computed by means of an XPath function that is evaluated at configuration time. An XPath function can either be a standard `xpath:<function>()` or a custom `cxpath:<function>()` function. The range of a configuration parameter may be computed based on other configuration parameters that are referenced from the XPath function. For more information on custom XPath functions, see section *Custom XPath Functions API* of the EB tresos Studio developer's guide.

Example: The parameter `BswMCompuConstText` of the `BswM` module of EB tresos AutoCore Generic 8 Mode Management has the custom XPath function `cxpath:getCompuMethodsVT()` in the range field which provides the allowed values.

5.2. Dccm

5.2.1. Configuration parameters

Containers included		
Container name	Multiplicity	Description
CommonPublishedInformation	1..1	Label: Common Published Information Common container, aggregated by all modules. It contains published information about vendor and versions.
DccmGeneral	1..1	Label: Dccm General Configuration This container contains the configuration parameters and sub containers of the Dccm module supporting multiple configuration sets. This container and its sub-containers exist once per configuration set.
DccmTimeouts	1..1	Label: Configure Dccm Timeouts. This container contains the Dccm timeout configuration.
DccmPhysicalPduals	0..255	Label: DccmPhysicalPduals Name of the Target ECU that shall be addressed for physical transmission.
DccmFunctionalPduals	0..255	Label: DccmFunctionalPduals Eculd of the target Ecu that shall be addressed for functional communication.
PublishedInformation	1..1	Label: EB Published Information Additional published parameters not covered by Common-PublishedInformation container.

5.2.1.1. CommonPublishedInformation

Parameters included	
Parameter name	Multiplicity
ArMajorVersion	1..1

Parameters included	
ArMinorVersion	1..1
ArPatchVersion	1..1
SwMajorVersion	1..1
SwMinorVersion	1..1
SwPatchVersion	1..1
ModuleId	1..1
VendorId	1..1
Release	1..1

Parameter Name	ArMajorVersion
Label	AUTOSAR Major Version
Description	Major version number of AUTOSAR specification on which the appropriate implementation is based on.
Multiplicity	1..1
Type	INTEGER_LABEL
Default value	0
Configuration class	PublishedInformation:
Origin	Elektrobit Automotive GmbH

Parameter Name	ArMinorVersion
Label	AUTOSAR Minor Version
Description	Minor version number of AUTOSAR specification on which the appropriate implementation is based on.
Multiplicity	1..1
Type	INTEGER_LABEL
Default value	0
Configuration class	PublishedInformation:
Origin	Elektrobit Automotive GmbH

Parameter Name	ArPatchVersion
Label	AUTOSAR Patch Version
Description	Patch level version number of AUTOSAR specification on which the appropriate implementation is based on.

Multiplicity	1..1
Type	INTEGER_LABEL
Default value	0
Configuration class	PublishedInformation:
Origin	Elektrobit Automotive GmbH

Parameter Name	SwMajorVersion
Label	Software Major Version
Description	Major version number of the vendor specific implementation of the module.
Multiplicity	1..1
Type	INTEGER_LABEL
Default value	2
Configuration class	PublishedInformation:
Origin	Elektrobit Automotive GmbH

Parameter Name	SwMinorVersion
Label	Software Minor Version
Description	Minor version number of the vendor specific implementation of the module. The numbering is vendor specific.
Multiplicity	1..1
Type	INTEGER_LABEL
Default value	0
Configuration class	PublishedInformation:
Origin	Elektrobit Automotive GmbH

Parameter Name	SwPatchVersion
Label	Software Patch Version
Description	Patch level version number of the vendor specific implementation of the module. The numbering is vendor specific.
Multiplicity	1..1
Type	INTEGER_LABEL
Default value	6
Configuration class	PublishedInformation:
Origin	Elektrobit Automotive GmbH

Parameter Name	ModuleId
Label	Numeric Module ID
Description	Module ID of this module from Module List
Multiplicity	1..1
Type	INTEGER_LABEL
Default value	255
Configuration class	PublishedInformation:
Origin	Elektrobit Automotive GmbH

Parameter Name	VendorId
Label	Vendor ID
Description	Vendor ID of the dedicated implementation of this module according to the AUTOSAR vendor list
Multiplicity	1..1
Type	INTEGER_LABEL
Default value	1
Configuration class	PublishedInformation:
Origin	Elektrobit Automotive GmbH

Parameter Name	Release
Label	Release Information
Multiplicity	1..1
Type	STRING_LABEL
Default value	
Configuration class	PublishedInformation:
Origin	Elektrobit Automotive GmbH

5.2.1.2. DccmGeneral

Parameters included	
Parameter name	Multiplicity
DccmMainfunctioCycle	1..1
Dccm_Dev_Error_Detect	1..1

Parameters included	
Dccm_Num_Of_Parallel_Diagnostic_Protocols	1..1
Dccm_Num_Of_Functional_Diagnostic_Protocols	1..1
Dccm_Buffer_Streaming	1..1
Dccm_Functional_Communication_With_No_Response_From_Server	1..1

Parameter Name	DccmMainfunctioCycle
Label	Periodic Task time
Description	<p>Configures the scheduling time for the periodic task in seconds.</p> <p>Dccm_MainFunction is executed after every DccmTaskTime.</p> <p>Note : Configured in seconds.</p>
Multiplicity	1..1
Type	FLOAT
Default value	0.005
Configuration class	VariantPreCompile: VariantPreCompile
Origin	AUTOSAR_ECUC

Parameter Name	Dccm_Dev_Error_Detect
Label	Enable Development Error Detection
Description	<p>Enables the error-reporting to the Development Error Tracer (DET).</p> <ul style="list-style-type: none"> ▶ TRUE: Development Error Detection mechanism is enabled (switched on). ▶ FALSE: Development Error Detection mechanism is disabled (switched off). <p>Optimization Effect:</p> <ul style="list-style-type: none"> ▶ ROM reduction (code): Disabling this parameter reduces the ROM consumption of the module code. ▶ Execution time reduction (code): Disabling this parameter reduces the execution time of the module code.
Multiplicity	1..1
Type	BOOLEAN
Default value	FALSE

Parameter Name	Dccm_Num_Of_Parallel_Diagnostic_Protocols
Label	Number of Parallel Diagnostic Protocols supported

Description	Sets the number of parallel diagnostic protocols supported. ▶ 1: Only one diagnostic protocol is supported. ▶ 2 . . . 255: Number of parallel diagnostic protocols.
Multiplicity	1..1
Type	INTEGER
Default value	8

Parameter Name	Dccm_Num_Of_Functional_Diagnostic_Protocols
Label	Number of Protocols reserved for Functional Communication
Description	Sets the number of diagnostic protocols used for functional communication. Must be smaller than the number of parallel diagnostic protocols.
Multiplicity	1..1
Type	INTEGER
Default value	0

Parameter Name	Dccm_Buffer_Streaming
Label	Enable Buffer Streaming
Description	Enables the buffer streaming. When a Dccm Request needs to transmit bigger quantity of data and not enough memory is available on the ECU the buffer streaming can be enabled. Enabling this will allow the client to provide a smaller buffer when calling the Dccm_SendRequest function and after that buffer data was provided to PduR then Dccm will request the next chunk of data from the client. ▶ TRUE: Buffer streaming is enabled (switched on). ▶ FALSE: Buffer streaming is disabled (switched off).
Multiplicity	1..1
Type	BOOLEAN
Default value	FALSE

Parameter Name	Dccm_Functional_Communication_With_No_Response_From_Server
Label	Functional Communication with no response from the server
Description	The server do not send any response for the requests that use functional communication. ▶ TRUE: In the case of functional communication, Dccm will consider that the server will not send any response. For the messages that are sent to the

	<p>server, Dccm will overwrite the value of the bit suppressPosRspMsgIndicationBit to TRUE.</p> <p>► FALSE: Dccm will consider that the server sends response for functional requests. The messages that are sent to the server are not modified by Dccm.</p>
Multiplicity	1..1
Type	BOOLEAN
Default value	FALSE

5.2.1.3. DccmTimeouts

Containers included		
Container name	Multiplicity	Description
DccmP2Client	0..1	Defines the configuration for the timeout P2Client. This container can be enabled only if the container for P6Client is disabled.
DccmP6Client	0..1	Defines the configuration for the timeout P6Client. This container can be enabled only if the container for P2Client is disabled.

Parameters included	
Parameter name	Multiplicity
DccmTimeoutInternal	1..1

Parameter Name	DccmTimeoutInternal
Label	Internal Timeout
Description	<p>This timer will start twice during the processing of a request:</p> <p>► 1) : Between start of transmission and confirmation of transmission for a request message. The start of transmission is triggered by the Dccm call of PduR_DccmTransmit(). The successful transmission of the request message is indicated via Dccm_TxConfirmation().</p> <p>► 2) : Between the start and the end of reception for the response message. The start of the response message is indicated via Dccm_StartOfReception(). The end of reception indicated via Dccm_RxIndication().</p> <p>Configurable time in milliseconds. Setting zero as value will disable this timeout.</p>
Multiplicity	1..1

Type	INTEGER
Default value	2000

5.2.1.4. DccmP2Client

Parameters included	
Parameter name	Multiplicity
DccmTimeoutP2Client	1..1
DccmTimeoutP2StarClient	1..1

Parameter Name	DccmTimeoutP2Client	
Label	DccmTimeoutP2Client	
Description	The P2Client represents the maximum amount of time in milliseconds between a successfully transmitted request and the start of the corresponding response. The successful transmission of the request message is indicated via Dccm_TxConfirmation(). The start of the response message is indicated via Dccm_StartOfReception().	
Multiplicity	1..1	
Type	INTEGER	
Default value	1000	
Range	<div><=4294967294</div> <div>>=1</div>	
Configuration class	VariantPreCompile:	VariantPreCompile

Parameter Name	DccmTimeoutP2StarClient	
Label	DccmTimeoutP2StarClient	
Description	The P2*Client represents the maximum amount of time in milliseconds between a response containing the negative response code 0x78 "requestCorrectlyReceived-ResponsePending" and the start of the next response. The reception of a negative response is indicated via Dccm_RxIndication(). The start of incoming response messages is indicated via Dccm_StartOfReception().	
Multiplicity	1..1	
Type	INTEGER	
Default value	8000	
Range	<=4294967294	

	>=1	
Configuration class	VariantPreCompile:	VariantPreCompile

5.2.1.5. DccmP6Client

Parameters included	
Parameter name	Multiplicity
DccmTimeoutP6Client	1..1
DccmTimeoutP6StarClient	1..1

Parameter Name	DccmTimeoutP6Client	
Label	DccmTimeoutP6Client	
Description	The P6Client represents the maximum amount of time in milliseconds between a successfully transmitted request and the complete reception of the corresponding response. The successful transmission of the request message is indicated via Dccm_TxConfirmation(). The complete reception of the response message is indicated via Dccm_RxIndication().	
Multiplicity	1..1	
Type	INTEGER	
Default value	3000	
Range	<=4294967294	
	>=1	
Configuration class	VariantPreCompile:	VariantPreCompile

Parameter Name	DccmTimeoutP6StarClient	
Label	DccmTimeoutP6StarClient	
Description	The P6*Client represents the maximum amount of time in milliseconds between a response containing the negative response code 0x78 "requestCorrectlyReceived-ResponsePending" and the complete reception of the response. The reception of a negative response is indicated via Dccm_RxIndication(). The complete reception of the response message is also indicated via Dccm_RxIndication().	
Multiplicity	1..1	
Type	INTEGER	
Default value	5000	

Range	<=4294967294	
	>=1	
Configuration class	VariantPreCompile:	VariantPreCompile

5.2.1.6. DccmPhysicalPduls

Parameters included	
Parameter name	Multiplicity
DccmPhysicalEculd	1..1
DccmPhysicalTxPduld	1..1
DccmPhysicalTxPduldRef	1..1
DccmPhysicalRxDuld	1..1
DccmPhysicalRxDuldRef	1..1

Parameter Name	DccmPhysicalEculd
Label	Eculd
Description	Eculd of the target Ecu that shall be addressed.
Multiplicity	1..1
Type	INTEGER

Parameter Name	DccmPhysicalTxPduld
Label	TxDuld
Description	Handle ID for the PDU used for physical transmission.
Multiplicity	1..1
Type	INTEGER

Parameter Name	DccmPhysicalTxPduldRef
Label	TxDuldRef
Multiplicity	1..1
Type	REFERENCE
Origin	EB

Parameter Name	DccmPhysicalRxDuld
Label	RxDuld

Description	Handle ID for the PDU used for physical transmission.
Multiplicity	1..1
Type	INTEGER

Parameter Name	DccmPhysicalRxPduIdRef
Label	RxPduIdRef
Multiplicity	1..1
Type	REFERENCE
Origin	EB

5.2.1.7. DccmFunctionalPduIds

Parameters included	
Parameter name	Multiplicity
DccmFunctionalEculd	1..1
DccmFunctionalTxPduId	1..1
DccmFunctionalTxPduIdRef	1..1
DccmFunctionalRxPduId	1..1
DccmFunctionalRxPduIdRef	1..1

Parameter Name	DccmFunctionalEculd
Label	Eculd
Description	Eculd of the target Ecu that shall be addressed.
Multiplicity	1..1
Type	INTEGER

Parameter Name	DccmFunctionalTxPduId
Label	TxPduId
Description	Handle ID for the PDU used for functional addressing.
Multiplicity	1..1
Type	INTEGER

Parameter Name	DccmFunctionalTxPduIdRef
Label	TxPduIdRef

Multiplicity	1..1
Type	REFERENCE
Origin	EB

Parameter Name	DccmFunctionalRxPduld
Label	RxPduld
Description	Handle ID for the PDU used for functional addressing.
Multiplicity	1..1
Type	INTEGER

Parameter Name	DccmFunctionalRxPduldRef
Label	RxRduldRef
Multiplicity	1..1
Type	REFERENCE
Origin	EB

5.2.1.8. PublishedInformation

Parameters included	
Parameter name	Multiplicity
PbcfgMSupport	1..1

Parameter Name	PbcfgMSupport	
Label	PbcfgM support	
Description	Specifies whether or not the Dccm can use the PbcfgM module for post-build support.	
Multiplicity	1..1	
Type	BOOLEAN	
Default value	false	
Configuration class	PublishedInformation:	
Origin	Elektrobit Automotive GmbH	

5.2.2. Application programming interface (API)

5.2.2.1. Type definitions

5.2.2.1.1. Dccm_BufferStreamingCallbackType

Purpose	Diagnostic Protocol Callback type to request next chunk of data in case Buffer Streaming is enabled.
Type	Std_ReturnType(*) (Dccm_ProtocolIdType ProtocolId, uint8 *Buffer, uint16 StartLocation, PduLengthType *AvailableDataPtr, uint8 RetryInformation)

5.2.2.1.2. Dccm_CallbackType

Purpose	Diagnostic Protocol Callback type to notify SW-Manager.
Type	void(*) (Dccm_ProtocolIdType ProtocolId, Dccm_DiagProtocolResponseCodeType ResponseCode)

5.2.2.1.3. Dccm_DiagProtocolResponseCodeType

Purpose	This type contains all Dccm Diagnostic Protocol result values, which can be reported via the callback method.
Type	uint8

5.2.2.1.4. Dccm_DiagnosticProtocolStatusType

Purpose	Status of a diagnostic protocol.
Type	uint8

5.2.2.1.5. Dccm_ProtocolIdType

Purpose	This type is used to identify the diagnostic protocol,.
Type	uint8

5.2.2.1.6. Dccm_TimeoutType

Purpose	Type for timeout counter.
Type	uint32

5.2.2.2. Macro constants

5.2.2.2.1. BITS3210_BIT_MASK

Purpose	Mask used to extract the low nibble from a specific parameter.
Value	0xFU

5.2.2.2.2. BITS_TO_SHIFT_4

Purpose	Mask used to shift an parameter with 4 bits,used especially to extract the high nibble.
Value	4U

5.2.2.2.3. BITS_TO_SHIFT_8

Purpose	Mask used to shift an parameter with 8 bits.
Value	8U

5.2.2.2.4. DCCM_BIT_MAPPED_REPORTED_WITH_OUT_MASK

Purpose	Macro for ReadScalingDataByIdentifier service which represents the bitMappedReportedWithOutMask encoding from scalingByte (High Nibble) parameter.
Value	0x2U

5.2.2.2.5. DCCM_BUFFER_STREAMING

Purpose	
----------------	--

Value	STD_ON
--------------	--------

5.2.2.2.6. DCCM_CLEAR_DYNAMICALLY_DEFINED_DATA_IDENTIFIER

Purpose	Macro used for DynamicallyDefineDataIdentifier service which represents the sub-function parameter when equals to 0x03 (clearDynamicallyDefinedDataIdentifier).
Value	0x03U

5.2.2.2.7. DCCM_DEFINE_BY_IDENTIFIER

Purpose	Macro used for DynamicallyDefineDataIdentifier service which represents the sub-function parameter when equals to 0x01 (defineByIdentifier).
Value	0x01U

5.2.2.2.8. DCCM_DEFINE_BY_MEMORY_ADDRESS

Purpose	Macro used for DynamicallyDefineDataIdentifier service which represents the sub-function parameter when equals to 0x02 (defineByMemoryAddress).
Value	0x02U

5.2.2.2.9. DCCM_DEV_ERROR_DETECT

Purpose	
Value	STD_ON

5.2.2.2.10. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_ALLOCATING

Purpose	The status of protocol that is currently going through the allocation process.
Value	0x01U

5.2.2.2.11. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_READY

Purpose	The status of protocol that is ready to start communication.
----------------	--

Value	0x02U
--------------	-------

5.2.2.2.12. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_READY_TO_TRANSMIT

Purpose	The status of a protocol that has finished processing a request and is ready to forward it.
Value	0x04U

5.2.2.2.13. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_RECEIVE

Purpose	The status of a protocol that is in the process of receiving the response.
Value	0x06U

5.2.2.2.14. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_RELEASE

Purpose	The status of protocol that is currently going through the release process.
Value	0x08U

5.2.2.2.15. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_SEND_NOTIFY

Purpose	The status of a protocol that has just finished receiving the response and is in the process of transmitting the callback to the Dccm client application.
Value	0x07U

5.2.2.2.16. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_SEND_RECEIVED

Purpose	The status of protocol that is currently going through processing a request.
Value	0x03U

5.2.2.2.17. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_TRANSMIT

Purpose	The transmission was triggered and the protocol is in the process of forwarding the message.
----------------	--

Value	0x05U
--------------	-------

5.2.2.2.18. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_TRANSMIT_REQUEST_NEXT_BUFFER

Purpose	The status of protocol when BufferStreaming is enabled and the transmission of the next data packet is requested.
Value	0x09U

5.2.2.2.19. DCCM_DIAGNOSTIC_PROTOCOL_STATUS_UNUSED

Purpose	The status of an unallocated protocol.
Value	0x00U

5.2.2.2.20. DCCM_DTCFORMAT_2

Purpose	Macro used for ReadDTCInformation service which represents the DTCFormatIdentifier parameter when equals to 0x2 (SAE_J1939-73_DTCFormat).
Value	0x2U

5.2.2.2.21. DCCM_DTCFORMAT_4

Purpose	Macro used for ReadDTCInformation service which represents the DTCFormatIdentifier parameter when equals to 0x4 (SAE_J2012-DA_DTCFormat_04).
Value	0x4U

5.2.2.2.22. DCCM_EXE_INTERVAL

Purpose	
Value	["num:i(\$UdsExeInterval)"]U

5.2.2.2.23. DCCM_E_INVALID_RESPONSE_FORMAT

Purpose	Response code when the response format is wrong.
----------------	--

Value	0x03U
--------------	-------

5.2.2.2.24. DCCM_E_INVALID_RESPONSE_LENGTH

Purpose	Response code when the response length is wrong.
Value	0x02U

5.2.2.2.25. DCCM_E_RESPONSE_PENDING

Purpose	Error code returned from server.
Value	0x78U

5.2.2.2.26. DCCM_FUNCTIONAL_COMM_NO_RESPONSE_EXPECTED

Purpose	
Value	STD_ON

5.2.2.2.27. DCCM_INVALID_PROTOCOL_ID

Purpose	A Protocol ID that is considered as invalid value.
Value	0xFFU

5.2.2.2.28. DCCM_LENGTH_0

Purpose	Macro representing the length of 0.
Value	0U

5.2.2.2.29. DCCM_LENGTH_1

Purpose	Macro representing the length of 1.
Value	1U

5.2.2.2.30. DCCM_LENGTH_2

Purpose	Macro representing the length of 2.
Value	2U

5.2.2.2.31. DCCM_LENGTH_3

Purpose	Macro representing the length of 3.
Value	3U

5.2.2.2.32. DCCM_LENGTH_4

Purpose	Macro representing the length of 4.
Value	4U

5.2.2.2.33. DCCM_LENGTH_5

Purpose	Macro representing the length of 5.
Value	5U

5.2.2.2.34. DCCM_LENGTH_6

Purpose	Macro representing the length of 6.
Value	6U

5.2.2.2.35. DCCM_LENGTH_7

Purpose	Macro representing the length of 7.
Value	7U

5.2.2.2.36. DCCM_LENGTH_8

Purpose	Macro representing the length of 8.
Value	8U

5.2.2.2.37. DCCM_MAX_DIAGNOSTIC_PROTOCOLS

Purpose	
Value	[! "num:integer(DccmGeneral/Dccm_Num_Of_Parallel_Diagnostic_Protocols")!]U

5.2.2.2.38. DCCM_MAX_DTC_EXT_DATA_RECORD_NR_16

Purpose	Macro used for ReadDTCInformation service which represents the maximum value for DTCExtDataRecordNumber parameter for 0x16 subfunction.
Value	0xEFU

5.2.2.2.39. DCCM_MAX_DTC_EXT_DATA_RECORD_NR_19

Purpose	Macro used for ReadDTCInformation service which represents the maximum value for DTCExtDataRecordNumber parameter for 0x19 subfunction.
Value	0xFEU

5.2.2.2.40. DCCM_MAX_DTC_EXT_DATA_RECORD_NR_6_10

Purpose	Macro used for ReadDTCInformation service which represents the maximum value for DTCExtDataRecordNumber parameter for 0x06 and 0x10 subfunctions.
Value	0xFDU

5.2.2.2.41. DCCM_MAX_PHYSICAL_DIAGNOSTIC_PROTOCOLS

Purpose	
Value	[! "num:integer(DccmGeneral/Dccm_Num_Of_Parallel_Diagnostic_Protocols - Dccm-General/Dccm_Num_Of_Functional_Diagnostic_Protocols")!]U

5.2.2.2.42. DCCM_MAX_SERVERS_FUNCTIONAL_ADDRESSING

Purpose	
Value	[! WS!] [! "\$Udsserversf"!]U

5.2.2.2.43. DCCM_MAX_SERVERS_PHYSICAL_ADDRESSING

Purpose	
Value	[!WS!][!"\$Udsservers"!U

5.2.2.2.44. DCCM_MODE_OF_OPERATION_DELETE_FILE

Purpose	Macro used for FileTransfer service which represents the modeOfOperation parameter when equals to 0x02 (DeleteFile).
Value	0x02U

5.2.2.2.45. DCCM_MODE_OF_OPERATION_READ_DIR

Purpose	Macro used for FileTransfer service which represents the modeOfOperation parameter when equals to 0x05 (ReadDir).
Value	0x05U

5.2.2.2.46. DCCM_P2CLIENT_ENABLED

Purpose	
Value	STD_ON

5.2.2.2.47. DCCM_P6CLIENT_ENABLED

Purpose	
Value	STD_ON

5.2.2.2.48. DCCM_READ_CURRENTLY_ACTIVE_TIMING_PARAMETERS

Purpose	Macro used for AccessTimingParameter service which represents the sub-function parameter when equals to 0x03 (readCurrentlyActiveTimingParameters).
Value	0x03U

5.2.2.2.49. DCCM_READ_EXTEND_TIMING_PARAMETER_SET

Purpose	Macro used for AccessTimingParameter service which represents the sub-function parameter when equals to 0x01 (readExtendedTimingParameterSet).
Value	0x01U

5.2.2.2.50. DCCM_RETRY_INFO_NULL

Purpose	Macro used to mark that the RetryInfoPtr parameter of the Dccm_CopyTxData() function is null.
Value	0x0FU

5.2.2.2.51. DCCM_RSP_INVALID_RESPONSE_PENDING_FORMAT

Purpose	Response to indicate that a ResponsePending message was received for another service, not the one for which the request was made.
Value	0x04U
Description	UdsC::UdsC_ResponseCode value provided to the upper module in the callback

5.2.2.2.52. DCCM_RSP_OK

Purpose	Requested service executed without error.
Value	0x00U
Description	Dccm::Dccm_ResponseCode value provided to the upper module in the callback

5.2.2.2.53. DCCM_RSP_RX_FAILED

Purpose	Data receiving failed.
Value	0x03U
Description	Dccm::Dccm_ResponseCode value provided to the upper module in the callback

5.2.2.2.54. DCCM_RSP_TIMEOUT

Purpose	Response code received from the (bottom module) PduR.
----------------	---

Value	0x07U
Description	Dccm::Dccm_ResponseCode value provided to the upper module in the callback

5.2.2.2.55. DCCM_RSP_TIMEOUT_INTERNAL

Purpose	No response from server during the internal timer.
Value	0x06U
Description	Dccm::Dccm_ResponseCode value provided to the upper module in the callback

5.2.2.2.56. DCCM_RSP_TIMEOUT_P2CLIENT

Purpose	No response from server during the P2Client or P2*Client timeout.
Value	0x05U
Description	Dccm::Dccm_ResponseCode value provided to the upper module in the callback

5.2.2.2.57. DCCM_RSP_TIMEOUT_P6CLIENT

Purpose	No response from server during the P6Client or P6*Client timeout.
Value	0x09U
Description	Dccm::Dccm_ResponseCode value provided to the upper module in the callback

5.2.2.2.58. DCCM_RSP_TX_FAILED

Purpose	Transmitting of data failed.
Value	0x01U
Description	Dccm::Dccm_ResponseCode value provided to the upper module in the callback

5.2.2.2.59. DCCM_RSP_TX_TRIG_FAILED

Purpose	Triggering of data transmit failed.
Value	0x02U
Description	Dccm::Dccm_ResponseCode value provided to the upper module in the callback

5.2.2.2.60. DCCM_RSP_WRONG_BUFFER_SIZE

Purpose	Receive buffer size is wrong.
Value	0x08U
Description	Dccm::Dccm_ResponseCode value provided to the upper module in the callback

5.2.2.2.61. DCCM_SCALING_BYTE_FORMULA

Purpose	Macro for ReadScalingDataByIdentifier service which represents the formula encoding from scalingByte (High Nibble) parameter.
Value	0x9U

5.2.2.2.62. DCCM_SCALING_BYTE_UNIT_FORMAT

Purpose	Macro for ReadScalingDataByIdentifier service which represents the unit/format encoding from scalingByte (High Nibble) parameter.
Value	0xAU

5.2.2.2.63. DCCM_SERVICE_ECU_RESET_SUBFUNCTION_ENABLE_RAPID_POWER_SHUTDOWN

Purpose	Macro used for EcuReset service which represents the sub-function parameter when equals to 0x04 (enableRapidPowerShutDown).
Value	0x04U

5.2.2.2.64. DCCM_STD_E_BUSY

Purpose	Dccm is busy at the moment: all available diagnostic protocols are in use.
Value	0x02U
Description	Dccm-specific Std_ReturnType value used by Dccm APIs

5.2.2.2.65. DCCM_SUBFUNCTION_MASK

Purpose	Mask used for subfunction to ignore the suppressPosRspMsgIndicationBit.
Value	0x7FU

5.2.2.2.66. DCCM_SUPPRESSBIT_MASK

Purpose	Mask used to extract only the suppressPosRspMsgIndicationBit.
Value	0x80U

5.2.2.2.67. DCCM_TIMEOUT_INTERNAL

Purpose	
Value	0xFFFFFFFFUL

5.2.2.2.68. DCCM_TIMEOUT_P2CLIENT

Purpose	
Value	["num:i(\$DccmTimeoutP2Client)"]UL

5.2.2.2.69. DCCM_TIMEOUT_P2STARCLIENT

Purpose	
Value	["num:i(\$DccmTimeoutP2StarClient)"]UL

5.2.2.2.70. DCCM_TIMEOUT_P6CLIENT

Purpose	
Value	["num:i(\$DccmTimeoutP6Client)"]UL

5.2.2.2.71. DCCM_TIMEOUT_P6STARCLIENT

Purpose	
Value	["num:i(\$DccmTimeoutP6StarClient)"]UL

5.2.2.2.72. DCCM_TX_CONFIRMATION_OK

Purpose	Response when Tx confirmation was OK and suppress bit is set.
----------------	---

Value	0x11U
Description	Dccm::Dccm_ResponseCode value provided to the upper module in the callback

5.2.2.2.73. DCCM_ZERO_SUBFUNCTION

Purpose	Macro which represents the sub-function parameter when equals to 0x00.
Value	0x00U

5.2.2.2.74. Dccm_ProvideRxBuffer

Purpose	Added for backward compatibility with old PduR implementations.
Value	Dccm_CopyRxData

5.2.2.2.75. Dccm_ProvideTxBuffer

Purpose	Added for backward compatibility with old PduR implementations.
Value	Dccm_CopyTxData

5.2.2.2.76. FUNCTIONAL_ADDRESSING

Purpose	Macro used to define AddressingType of a diagnostic protocol.
Value	1U

5.2.2.2.77. MAX_NO_OF_SERVICES

Purpose	Maximum number of services.
Value	26U

5.2.2.2.78. NEGATIVE_RESPONSE_LENGTH

Purpose	The length of a negative response.
Value	3U

5.2.2.2.79. NEGATIVE_RESPONSE_SID

Purpose	Service Id for an negative response message.
Value	0x7FU

5.2.2.2.80. PHYSICAL_ADDRESSING

Purpose	Macro used to define AddressingType of a diagnostic protocol.
Value	0U

5.2.2.2.81. SID_ACCESS_TIMING_PARAMETER

Purpose	Service Id for access timing parameter request.
Value	0x83U

5.2.2.2.82. SID_ACCESS_TIMING_PARAMETER_RSP

Purpose	Service Id for access timing response.
Value	0xC3U

5.2.2.2.83. SID_CLEAR_DIAGNOSTIC_INFORMATION

Purpose	Service Id for clear diagnostic information request.
Value	0x14U

5.2.2.2.84. SID_CLEAR_DIAGNOSTIC_INFORMATION_RSP

Purpose	Service Id for clear diagnostic information response.
Value	0x54U

5.2.2.2.85. SID_COMMUNICATION_CONTROL

Purpose	Service Id for communication control request.
----------------	---

Value	0x28U
--------------	-------

5.2.2.2.86. SID_COMMUNICATION_CONTROL_RSP

Purpose	Service Id for communication control response.
Value	0x68U

5.2.2.2.87. SID_CONTROL_DTC_SETTING

Purpose	Service Id for control dtc setting request.
Value	0x85U

5.2.2.2.88. SID_CONTROL_DTC_SETTING_RSP

Purpose	Service Id for control dtc setting response.
Value	0xC5U

5.2.2.2.89. SID_DIAGNOSTIC_SESSION_CONTROL

Purpose	Service Id for diagnostic session control request.
Value	0x10U

5.2.2.2.90. SID_DIAGNOSTIC_SESSION_CONTROL_RSP

Purpose	Service Id for diagnostic session response.
Value	0x50U

5.2.2.2.91. SID_DYNAMICALLY_DEFINE_DATA_IDENTIFIER

Purpose	Service Id for dynamically define data identifier request.
Value	0x2CU

5.2.2.2.92. SID_DYNAMICALLY_DEFINE_DATA_IDENTIFIER_RSP

Purpose	Service Id for dynamically define data identifier response.
Value	0x6CU

5.2.2.2.93. SID_ECU_RESET

Purpose	Service Id for ecu reset request.
Value	0x11U

5.2.2.2.94. SID_ECU_RESET_RSP

Purpose	Service Id for ecu reset response.
Value	0x51U

5.2.2.2.95. SID_FILE_TRANSFER

Purpose	Service Id for file transfer request.
Value	0x38U

5.2.2.2.96. SID_FILE_TRANSFER_RSP

Purpose	Service Id for file transfer response.
Value	0x78U

5.2.2.2.97. SID_INPUT_OUTPUT_CONTROL_BY_IDENTIFIER

Purpose	Service Id for input output control by identifier request.
Value	0x2FU

5.2.2.2.98. SID_INPUT_OUTPUT_CONTROL_BY_IDENTIFIER_RSP

Purpose	Service Id for input output control by identifier response.
----------------	---

Value	0x6FU
--------------	-------

5.2.2.2.99. SID_LINK_CONTROL

Purpose	Service Id for link control request.
Value	0x87U

5.2.2.2.100. SID_LINK_CONTROL_RSP

Purpose	Service Id for link control response.
Value	0xC7U

5.2.2.2.101. SID_READ_DATA_BY_IDENTIFIER

Purpose	Service Id for read data by identifier request.
Value	0x22U

5.2.2.2.102. SID_READ_DATA_BY_IDENTIFIER_RSP

Purpose	Service Id for read data by identifier response.
Value	0x62U

5.2.2.2.103. SID_READ_DATA_BY_PERIODIC_IDENTIFIER

Purpose	Service Id for read data by periodic identifier request.
Value	0x2AU

5.2.2.2.104. SID_READ_DATA_BY_PERIODIC_IDENTIFIER_RSP

Purpose	Service Id for read data by periodic identifier response.
Value	0x6AU

5.2.2.2.105. SID_READ_DTC_INFORMATION

Purpose	Service Id for read dtc information request.
Value	0x19U

5.2.2.2.106. SID_READ_DTC_INFORMATION_RSP

Purpose	Service Id for read dtc information response.
Value	0x59U

5.2.2.2.107. SID_READ_MEMORY_BY_ADDRESS

Purpose	Service Id for read memory by address request.
Value	0x23U

5.2.2.2.108. SID_READ_MEMORY_BY_ADDRESS_RSP

Purpose	Service Id for read memory by address response.
Value	0x63U

5.2.2.2.109. SID_READ_SCALING_DATA_BY_IDENTIFIER

Purpose	Service Id for read scaling data by identifier request.
Value	0x24U

5.2.2.2.110. SID_READ_SCALING_DATA_BY_IDENTIFIER_RSP

Purpose	Service Id for read scaling data by identifier response.
Value	0x64U

5.2.2.2.111. SID_REQUEST_DOWNLOAD

Purpose	Service Id for request download request.
Value	0x34U

5.2.2.2.112. SID_REQUEST_DOWNLOAD_RSP

Purpose	Service Id for request download response.
Value	0x74U

5.2.2.2.113. SID_REQUEST_TRANSFER_EXIT

Purpose	Service Id for transfer exit request.
Value	0x37U

5.2.2.2.114. SID_REQUEST_TRANSFER_EXIT_RSP

Purpose	Service Id for request transfer exit response.
Value	0x77U

5.2.2.2.115. SID_REQUEST_UPLOAD

Purpose	Service Id for request upload request.
Value	0x35U

5.2.2.2.116. SID_REQUEST_UPLOAD_RSP

Purpose	Service Id for request upload response.
Value	0x75U

5.2.2.2.117. SID_RESPONSE_ON_EVENT

Purpose	Service Id for response on event request.
Value	0x86U

5.2.2.2.118. SID_RESPONSE_ON_EVENT_RSP

Purpose	Service Id for response on event response.
Value	0xC6U

5.2.2.2.119. SID_ROUTINE_CONTROL

Purpose	Service Id for routine control request.
Value	0x31U

5.2.2.2.120. SID_ROUTINE_CONTROL_RSP

Purpose	Service Id for routine control response.
Value	0x71U

5.2.2.2.121. SID_SECURED_DATA_TRANSMISSION

Purpose	Service Id for secured data transmission request.
Value	0x84U

5.2.2.2.122. SID_SECURED_DATA_TRANSMISSION_RSP

Purpose	Service Id for secured data transmission response.
Value	0xC4U

5.2.2.2.123. SID_SECURITY_ACCESS

Purpose	Service Id for security access request.
Value	0x27U

5.2.2.2.124. SID_SECURITY_ACCESS_RSP

Purpose	Service Id for security access response.
Value	0x67U

5.2.2.2.125. SID_TESTER_PRESENT

Purpose	Service Id for tester present request.
Value	0x3EU

5.2.2.2.126. SID_TESTER_PRESENT_RSP

Purpose	Service Id for tester present response.
Value	0x7EU

5.2.2.2.127. SID_TRANSFER_DATA

Purpose	Service Id for transfer data request.
Value	0x36U

5.2.2.2.128. SID_TRANSFER_DATA_RSP

Purpose	Service Id for transfer data response.
Value	0x76U

5.2.2.2.129. SID_WRITE_DATA_BY_IDENTIFIER

Purpose	Service Id for write data by identifier request.
Value	0x2EU

5.2.2.2.130. SID_WRITE_DATA_BY_IDENTIFIER_RSP

Purpose	Service Id for write data by identifier response.
Value	0x6EU

5.2.2.2.131. SID_WRITE_MEMORY_BY_ADDRESS

Purpose	Service Id for write memory by address request.
Value	0x3DU

5.2.2.2.132. SID_WRITE_MEMORY_BY_ADDRESS_RSP

Purpose	Service Id for write memory by address response.
Value	0x7DU

5.2.2.3. Functions

5.2.2.3.1. Dccm_AllocateDiagnosticProtocol

Purpose	An interface to allocate a diagnostic protocol.	
Synopsis	<pre>Std_ReturnType Dccm_AllocateDiagnosticProtocol (uint16 TxPduId , uint16 RxPduId , Dccm_ProtocolIdType * ProtocolId , uint8 Ad- dressingType , Dccm_CallbackType Callback , Dccm_BufferStream- ingCallbackType BufferStreamingCallback);</pre>	
Service ID	Dccm_AllocateDiagnosticProtocol	
Sync/Async	Synchronous	
Reentrancy	Reentrant for different PduIds. Non reentrant for the same PduId	
Parameters (in)	TxPduId	The PduId that will be used for sending data.
	RxPduId	The PduId that will be used for receiving data.
	AddressingType	The protocol is allocated for physical or functional communication. Expected values: PHYSICAL_ADDRESSING or FUNCTIONAL_ADDRESSING.
	Callback	The callback function that will be used by the Dccm to inform the caller of a service about the result.
	BufferStreamingCallback	The callback function that will be used by the Dccm to ask the next data packet from the client application in the use-case with buffer streaming. If BufferStreaming is not activated this parameter should be null pointer.
Parameters (out)	ProtocolId	The ID of the protocol will be returned to the caller of the function.
Return Value	Std_ReturnType	
	E_OK	The protocol was allocated
	E_NOT_OK	There was an error related with the parameters provided to the function. The ProtocolId OUT parameter contains a value that is not valid (DCCM_INVALID_PRO-

		TOCOL_ID). The maximum number of diagnostic protocols used for physical communication has been reached.
	DCCM_STD_E_BUSY	There are no available protocols. After a protocol will be released by the client application, it can be allocated again.
Description	<p>This function is used to allocate a diagnostic protocol. It shall be called before sending an Dccm Request. If BufferStreaming is not activated the parameter BufferStreaming-Callback should be null pointer.</p> <p>The application that is the client of Dccm can not communicate with a sever without first allocating a diagnostic protocol. The number of available diagnostic protocols is limited by:</p> <ul style="list-style-type: none"> ▶ the total number of protocols that is configured for the Dccm module, ▶ the number of protocols previously allocated by the client application, and ▶ the number of protocols reserved for functional communication (from the configuration of Dccm). <p>From the total number of protocols, the client of the Dccm module can use any number of protocols for functional communication, but the number of protocols available for physical communication is just the difference between the total number of protocols and the number of protocols reserved for functional communication.</p> <p>A specific TxPduld can be used only once, for a single Dccm communication protocol. A specific RxPduld can be used only once, for a single Dccm communication protocol.</p> <p>Configuration: The maximum number of parallel diagnostic protocols can be configured but is limited to maximum 255.</p>	

5.2.2.3.2. Dccm_CheckBufferSuppressBit

Purpose	Check the Buffer for Suppress Bit.
Synopsis	<pre>boolean Dccm_CheckBufferSuppressBit (uint16 DataLength , uint8 * Buffer);</pre>
Service ID	Dccm_CheckBufferSuppressBit
Sync/Async	Synchronous
Reentrancy	Non reentrant
Return Value	boolean

	TRUE	bit is set
	FALSE	bit is not set
Description	<p>This function checks if the suppress positive response message indication bit is set in the input buffer.</p> <p>Configuration: No configuration is needed for this function</p>	

5.2.2.3.3. Dccm_CheckResponsePending

Purpose	Check the Buffer for Response Pending message.	
Synopsis	<pre>boolean Dccm_CheckResponsePending (uint16 DataLength , uint8 * Buffer);</pre>	
Service ID	Dccm_CheckResponsePending	
Sync/Async	Synchronous	
Reentrancy	Non reentrant	
Return Value	Std_ReturnType	
	TRUE	if the response pending is set
	FALSE	the buffer is not big enough or if the response pending is not set
Description	<p>This function is used to check if the Response Pending message has been set in the input buffer.</p> <p>Configuration: No configuration is needed for this function</p>	

5.2.2.3.4. Dccm_CopyRxData

Purpose	API to copy data from receive buffer.	
Synopsis	<pre>BufReq_ReturnType Dccm_CopyRxData (PduIdType RxPduId , PduInfoType * PduInfoPtr , PduLengthType * RxBufferSizePtr);</pre>	
Service ID	Dccm_CopyRxData	
Sync/Async	Synchronous	
Reentrancy	Reentrant for different PduIds. Non reentrant for the same PduId	
Parameters (in)	RxPduId	- Dccm handle ID to be used for Dccm APIs to be called from PduR.

	PduInfoPtr	- Pointer providing received data and data length.
Parameters (out)	RxBufferSizePtr	- The number of bytes that are still unused in the receive buffer, and that can be used to store the next data packages that will be received.
Return Value	BufReq_ReturnType	
	BUFREQ_OK	- Data is copied.
	BUFREQ_E_NOT_OK	- Request failed.
Description	This function copies the TpRx data to the Dccm receive buffer.	

5.2.2.3.5. Dccm_CopyTxData

Purpose	API to request data to transmit.	
Synopsis	BufReq_ReturnType Dccm_CopyTxData (PduIdType TxPduId , PduInfoType * PduInfoPtr , RetryInfoType * RetryInfoPtr , PduLengthType * AvailableDataPtr);	
Service ID	Dccm_CopyTxData	
Sync/Async	Synchronous	
Reentrancy	Reentrant for different PduIds. Non reentrant for the same PduId	
Parameters (in)	TxPduId	- Dccm handle ID to be used for Dccm APIs to be called from PduR.
	PduInfoPtr	- Pointer providing a buffer and length to copy the Tx data.
	RetryInfoPtr	- This parameter is used to acknowledge transmitted data or to retransmit data after transmission problems. Please see the document Autosar SWS for PduRouter for details.
Parameters (out)	AvailableDataPtr	- Pointer which returns remaining number of bytes to be copied. Eg.: from a total of 10 bytes, only 3 were transmitted during the current call of Dccm_CopyTxData() , so AvailableDataPtr will show that there are 7 bytes that wait to be transmitted, with further calls to the same function Dccm_CopyTxData() .

Return Value	BufReq_ReturnType	
	BUFREQ_OK	- Data is copied.
	BUFREQ_E_BUSY	- The number of bytes that still wait to be transmitted, after the call to this function ends. Eg.: from a total of 10 bytes, only 3 were transmitted during the current call of Dccm_CopyTxData() , so AvailableDataPtr will show that there are 7 bytes that wait to be transmitted, with further calls to the same function Dccm_CopyTxData() .
	BUFREQ_E_NOT_OK	- Request failed.
Description	This function copies the Dccm transmit data to the CanTp transmit buffer.	

5.2.2.3.6. Dccm_DisableTesterPresent

Purpose	Disable the periodic sending of tester present.	
Synopsis	Std_ReturnType Dccm_DisableTesterPresent (Dccm_ProtocolIdType ProtocolId);	
Service ID	Dccm_DisableTesterPresent	
Sync/Async	Synchronous	
Reentrancy	Reentrant for different PduIds. Non reentrant for the same PduId	
Parameters (in)	ProtocolId	The ID of the Dccm protocol.
Return Value	Std_ReturnType	
	E_OK	TesterPresent functional message was disabled for the Dccm protocol ProtocolId.
	E_NOT_OK	There was an error: <ul style="list-style-type: none"> ▶ the sending of the message Tester-Present is not enabled for the ProtocolId provided as input parameter, or ▶ the ProtocolId is not valid, or ▶ the module was not properly initialized.
Description	This function is used to disable the periodic sending of tester present for the ProtocolId provided. Use-case 1: if the sending of the TesterPresent message is not ongoing, TesterPresent will be disabled during the call of this function. Use-case 2: if the	

	<p>sending of the TesterPresent message was already triggered by Dccm, Dccm will disable the periodic sending of TesterPresent message after the invocation of Dccm_TxConfirmation(), in the next call of Dccm_MainFunction(). Until then, Dccm_IsTesterPresentEnabled() will return false.</p>
--	---

5.2.2.3.7. Dccm_EnableTesterPresent

Purpose	Enable the periodic sending of the TesterPresent message.	
Synopsis	<pre>Std_ReturnType Dccm_EnableTesterPresent (Dccm_ProtocolIdType ProtocolId , uint8 * Buffer , uint16 BufferLength , uint16 * DataLengthPtr);</pre>	
Service ID	Dccm_EnableTesterPresent	
Sync/Async	Synchronous	
Reentrancy	Reentrant for different PduIds. Non reentrant for the same PduId	
Parameters (in)	ProtocolId	The ID of the Dccm protocol.
	BufferLength	- should be at least 3 bytes length, to have enough room for a negative response from the server
Parameters (out)	Buffer	- the content of buffer is ignored
	DataLengthPtr	- will contain the answer from the server (if it is received)
Return Value	Std_ReturnType	
	E_OK	Status was retrieved and returned to the user
	E_NOT_OK	ProtocolId not correct, buffer is too short, Buffer is null, DataLengthPtr is null, no functional address is set in the configuration of Dccm, BufferLength is smaller than 3, the protocol identified with ProtocolId was not allocated for functional communication, or the function Dccm_SetTesterPresentInterval() was not yet called.
Description	<p>This function is used to enable the periodic sending of the TesterPresent message on a specific Dccm protocol. Dccm_SetTesterPresentInterval() must be called before the call to this function. In Dccm, the TesterPresent functionality can be used only for functional communication. Because of this limitation, the Dccm protocol must be allocated specifically for functional communication.</p>	

5.2.2.3.8. Dccm_GetDiagnosticProtocolStatus

Purpose	Returns the status of a Diagnostic Protocol.	
Synopsis	<pre>Std_ReturnType Dccm_GetDiagnosticProtocolStatus (Dccm_ProtocolIdType ProtocolId , Dccm_DiagnosticProtocolStatusType * Status);</pre>	
Service ID	Dccm_GetDiagnosticProtocolStatus	
Sync/Async	Synchronous	
Reentrancy	Reentrant for different PduIds. Non reentrant for the same PduId	
Parameters (in)	ProtocolId	The status of this protocol ID is queried.
Parameters (out)	Status	This is the status of the protocol that is returned to the user.
Return Value	Std_ReturnType	
	E_OK	Status was retrieved and returned to the user
	E_NOT_OK	ProtocolID is out of the pre-configured range of values, or the Status parameter is null.
Description	This function is used to query the status of a specific Diagnostic Protocol.	

5.2.2.3.9. Dccm_Init

Purpose	Initializes or reinitializes the Dccm module.
Synopsis	<pre>void Dccm_Init (void);</pre>
Service ID	Dccm_Init
Sync/Async	Synchronous
Reentrancy	Non reentrant
Description	<p>This function resets all relevant variables to the default values.</p> <p>This function shall be used during the startup phase of the ECU after the NVRAM Manager has finished the restore of NVRAM data.</p> <p>SW-Components including Monitor Functions are initialized afterwards.</p> <p>Caveats: The Dccm is not functional until this function has been called.</p>

5.2.2.3.10. Dccm_IsTesterPresentEnabled

Purpose	Check if the tester present is enabled or not.	
Synopsis	Std_ReturnType Dccm_IsTesterPresentEnabled (Dccm_ProtocolId-Type ProtocolId , boolean * IsTesterPresentEnabled);	
Service ID	Dccm_IsTesterPresentEnabled	
Sync/Async	Synchronous	
Reentrancy	Reentrant for different PduIds. Non reentrant for the same PduId	
Parameters (in)	ProtocolId	The ID of the Dccm protocol.
Parameters (out)	IsTesterPresentEnabled	will be TRUE if TesterPresent notification is enabled for the protocol with the ID ProtocolId.
Return Value	Std_ReturnType	
	E_OK	Status was retrieved and returned to the user
	E_NOT_OK	the ProtocolId is not good, or IsTesterPresentEnabled is NULL.
Description	This function will return the status of tester present for the selected Dccm protocol.	

5.2.2.3.11. Dccm_MainFunction

Purpose	Processes the Dccm requests.
Synopsis	void Dccm_MainFunction (void);
Service ID	Dccm_MainFunction
Sync/Async	Synchronous
Reentrancy	Non reentrant
Description	<p>This function is used to process the Dccm requests. It shall be called periodically as a cyclic task by the software system (e.g. by operating system). If a Main function of a un-initialized module is called from the BSW Scheduler, then it shall return immediately without performing any functionality and without raising any errors.</p> <p>Timing: fixed cyclic</p> <p>Configuration: The cyclic time for the main function has to be defined as an operating system task or runnable entity.</p>

5.2.2.3.12. Dccm_ReleaseAllDiagnosticProtocols

Purpose	An interface to release all the Dccm Diagnostic Protocols.	
Synopsis	<code>Std_ReturnType Dccm_ReleaseAllDiagnosticProtocols (void);</code>	
Service ID	Dccm_ReleaseAllDiagnosticProtocols	
Sync/Async	Synchronous	
Reentrancy	Non reentrant	
Return Value	Std_ReturnType	
	E_OK	All the diagnostic protocols were properly released. Non-releasable statuses: RELEASE or ALLOCATING.
	E_NOT_OK	No protocol has been released because at least one protocol is still in one of the following situations: <ul style="list-style-type: none"> ▶ the state is RELEASE or ALLOCATING; ▶ or the TesterPresent feature is enabled and the sending of the TesterPresent message is on-going.
Description	<p>This function is used to release all allocated diagnostic protocols It shall be called when there is no need for communication.</p> <p>Configuration: The maximum number of parallel diagnostic protocols can be configured but is limited to maximum 255 (0x00 - 0xFE: 0U - 254U).</p>	

5.2.2.3.13. Dccm_ReleaseDiagnosticProtocol

Purpose	An interface to release a Dccm Diagnostic Protocol.
Synopsis	<code>Std_ReturnType Dccm_ReleaseDiagnosticProtocol (Dccm_ProtocolIdType ProtocolId);</code>
Service ID	Dccm_ReleaseDiagnosticProtocol
Sync/Async	Synchronous
Reentrancy	Reentrant for different PduIds. Non reentrant for the same PduId

Parameters (in)	ProtocolId	Release the protocol with this ID.
Return Value	Std_ReturnType	
	E_OK	The protocol was released
	E_NOT_OK	The ProtocolID is outside of the pre-configured range of values, or the protocol identified with this ProtocolID is in one of the following states: UNUSED, RELEASE, ALLOCATING.
Description	<p>This function is used to release a diagnostic protocol It shall be called when there is no need for communication over the specific PduId. If TesterPresent is enabled for the current protocol, Dccm will take care to disable the TesterPresent sending.</p> <p>Configuration: The maximum number of parallel diagnostic protocols can be configured but is limited to maximum 255 (0x00 - 0xFE: 0U - 254U).</p>	

5.2.2.3.14. Dccm_RxIndication

Purpose	API to indicate that all receptions have finished.	
Synopsis	<pre>void Dccm_RxIndication (PduIdType RxPduId , NotifResultType Result);</pre>	
Service ID	Dccm_RxIndication	
Sync/Async	Synchronous	
Reentrancy	Reentrant for different PduIds. Non reentrant for the same PduId	
Parameters (in)	RxPduId	- Dccm handle ID to be used for Dccm APIs to be called from PduR.
	Result	- Result of the finished reception.
Description	This function will be called if data has been received.	

5.2.2.3.15. Dccm_SendRequest

Purpose	Sends an UDS payload over a Diagnostic Protocol.	
Synopsis	<pre>Std_ReturnType Dccm_SendRequest (Dccm_ProtocolIdType ProtocolId , uint8 * Buffer , uint16 BufferLength , uint16 * DataLengthPtr);</pre>	

Service ID	Dccm_SendRequest	
Sync/Async	Asynchronous	
Reentrancy	Reentrant for different PduIds. Non reentrant for the same PduId	
Parameters (in)	ProtocolId	The Protocol ID that will be used in the communication with the server.
	BufferLength	Size of the buffer.
Parameters (in,out)	Buffer	A pointer to the start of the buffer where the data received from the server will be stored.
	DataLengthPtr	IN: The number of bytes that will be sent to the server. OUT: A pointer to return the number of bytes received from the server.
Return Value	Std_ReturnType	
	E_OK	Service accepted
	E_NOT_OK	ProtocolId not correct, buffer is too short, Buffer is null or DataLengthPtr is null.
	DCCM_STD_E_BUSY	A request is active.
Description	<p>This function is used to initiate the sending of the UDS payload over a Diagnostic Protocol. The Diagnostic Protocol should be in the READY state otherwise the call will return with error.</p> <p>Configuration: The maximum number of parallel diagnostic protocols can be configured but is limited to maximum 255. The PduIds should be configured and the function will check if the provided PduId is not over the limit.</p>	

5.2.2.3.16. Dccm_SetCommunicationTimeoutParameters

Purpose	Set the timeout parameters for a specific diagnostic protocol.	
Synopsis	<pre>Std_ReturnType Dccm_SetCommunicationTimeoutParameters (Dccm_ProtocolIdType ProtocolId , Dccm_TimeoutType P2ClientConfigurationValue , Dccm_TimeoutType InternalTimeout , Dccm_TimeoutType P2StarClientConfigurationValue);</pre>	
Service ID	Dccm_SetCommunicationTimeoutParameters	
Sync/Async	Synchronous	
Reentrancy	Reentrant for different PduIds. Non reentrant for the same PduId	
Parameters (in)	ProtocolId	The ID of the Dccm protocol.

	P2ClientConfigurationValue	The value to be used for the start of P2Client timeout.
	InternalTimeout	The value to be used for the start of internal timeout.
	P2StarClientConfigurationValue	The value to be used for the start of P2StarClient timeout.
Return Value	Std_ReturnType	
	E_OK	Diagnostic Protocol communication parameters were successfully updated
	E_NOT_OK	the ProtocolId is not valid or not in the DCCM_DIAGNOSTIC_PROTOCOL_STATUS_READY
Description	This function is used to set the timeout parameters for a specific diagnostic protocol. Depending on the configuration, the input parameters may be P2ClientConfigurationValue and P2StarClientConfigurationValue or P6ClientConfigurationValue and P6StarClientConfigurationValue.	

5.2.2.3.17. Dccm_SetTesterPresentInterval

Purpose	Set the time interval the periodic sending of the TesterPresent message.	
Synopsis	void Dccm_SetTesterPresentInterval (uint16 Interval);	
Service ID	Dccm_SetTesterPresentInterval	
Sync/Async	Synchronous	
Reentrancy	Non reentrant	
Parameters (in)	Interval	<p>The time interval between initiating two consecutive TesterPresent messages. The value should be long enough to permit the proper sending of the messages:</p> <ul style="list-style-type: none"> ▶ Dccm_MainFunction() must be called a number of times to assure that the protocols switch through a number of states; ▶ PduR must have enough time to call the call-back functions (provided by Dccm) involved in the sending of the messages.

Description	This function is used to set the time interval the periodic sending of the TesterPresent message.
--------------------	---

5.2.2.3.18. Dccm_StartOfReception

Purpose	API to start a reception.	
Synopsis	<pre>BufReq_ReturnType Dccm_StartOfReception (PduIdType RxPduId , PduLengthType TpTotalLength , PduLengthType * RxBufferSizePtr);</pre>	
Service ID	Dccm_StartOfReception	
Sync/Async	Synchronous	
Reentrancy	::Reentrant for different PduIds. Non reentrant for the same PduId	
Parameters (in)	RxPduId	- Dccm handle ID to be used for Dccm APIs to be called from PduR.
	TpTotalLength	- Message length.
Parameters (out)	RxBufferSizePtr	Available Rx buffer in the Dccm module.
Return Value	BufReq_ReturnType	
	BUFREQ_OK	- Reception request has been accepted. RxBufferSizePtr indicates the available receive buffer.
	BUFREQ_E_NOT_OK	- Reception request has been rejected. RxBufferSizePtr remains unchanged.
Description	This function is called once by PduR if a connection has been established.	

5.2.2.3.19. Dccm_TxConfirmation

Purpose	API to confirm a TCP transmission.	
Synopsis	<pre>void Dccm_TxConfirmation (PduIdType TxPduId , NotifResultType Result);</pre>	
Service ID	Dccm_TxConfirmation	
Sync/Async	Synchronous	
Reentrancy	Reentrant for different PduIds. Non reentrant for the same PduId	
Parameters (in)	TxPduId	- Dccm handle ID to be used for Dccm APIs to be called from PduR.

	Result	- Parameter indicates the result of the transmission.
Description	This function indicates if the transmission was successful.	

5.2.2.3.20. Dccm_ValidateRespBasedOnRequest

Purpose	This function validates a response based on request.	
Synopsis	Std_ReturnType Dccm_ValidateRespBasedOnRequest (uint8 * RequestBuffer , uint32 RequestDataLength , uint8 * ResponseBuffer , uint32 ResponseDataLength);	
Parameters (in)	RequestBuffer	The request buffer used for validation.
	RequestDataLength	The length of the request.
Return Value	ResponseBuffer	The response buffer to be validated.
	ResponseDataLength	The length of the response.
	Std_ReturnType	
	E_OK	The response buffer is correct.
	E_NOT_OK	The parameters that the function was called up are invalid or the minimum length of request required to perform the checks is not met.
	DCCM_E_INVALID_RESPONSE_LENGTH	The positive response may have a fixed length or may be a changeable length. If the length varies the function will only check the minimum length. For negative response length should be 3 bytes. If the length does not meet the requirements stated above, this error will be returned.
Description	DCCM_E_INVALID_RESPONSE_FORMAT	The SID from the positive response does not match the SID that should follow the request; the 2nd byte of the negative response is not the SID in the request; if the service has a DID, sub-function or a byte that must be echo, those that come in response do not match those in the request.
	The function is used to validate a response based on the request in terms of length and format.	

5.2.3. Integration notes

5.2.3.1. Exclusive areas

This section describes the exclusive areas used by the `Dccm` module.

5.2.3.2. Production errors

The module does not report any production errors.

5.2.3.3. Memory mapping

General information about memory mapping is provided in the EB tresos AutoCore Generic documentation. Refer to the section `Memory mapping and compiler abstraction` in the `Integration notes` section for details.

The following table provides the list of sections that may be mapped for this module:

Memory section
CONFIG_DATA_UNSPECIFIED
VAR_INIT_UNSPECIFIED
VAR_NO_INIT_UNSPECIFIED
CONST_UNSPECIFIED
INTERNAL_VAR_POWER_ON_INIT_UNSPECIFIED
CODE
VAR_NO_INIT_8
VAR_POWER_ON_INIT_32

5.2.3.4. Integration requirements

WARNING



Integration requirements list is not exhaustive

The following list of integration requirements helps you to integrate your product. However, this list is not exhaustive. You also require information from the user guide, release notes, and EB tresos AutoCore known issues to successfully integrate your product.

Integration requirements are not listed for the `Dccm` module.



5.2.3.5. Platform integration

Search for `Platforms Setting` in the source code of the Dccm plugin or in this document to find all locations where a platform specific setting is required.

Bibliography

- [1] *Specification of Platform Types, AUTOSAR 4.0.3*
- [2] *Specification of Compiler Abstraction, AUTOSAR 4.0.3*
- [3] *Specification of Memory Mapping, AUTOSAR 4.0.3*
- [4] *Road vehicles - Unified diagnostic services (UDS) ISO14229-1, 2013*
- [5] *Road vehicles - Unified diagnostic services (UDS) ISO14229-2, 2013*